



COMSOL Multiphysics®

Installation Guide



VERSION 4.4



COMSOL Installation Guide

© 1998–2013 COMSOL

Protected by U.S. Patents 7,519,518; 7,596,474; 7,623,991; and 8,457,932. Patents pending.

This Documentation and the Programs described herein are furnished under the COMSOL Software License Agreement (www.comsol.com/comsol-license-agreement) and may be used or copied only under the terms of the license agreement.

COMSOL, COMSOL Multiphysics, Capture the Concept, COMSOL Desktop, and LiveLink are either registered trademarks or trademarks of COMSOL AB. All other trademarks are the property of their respective owners, and COMSOL AB and its subsidiaries and products are not affiliated with, endorsed by, sponsored by, or supported by those trademark owners. For a list of such trademark owners, see www.comsol.com/trademarks.

Version:

November 2013

COMSOL 4.4

Contact Information

Visit the Contact COMSOL page at www.comsol.com/contact to submit general inquiries, contact Technical Support, or search for an address and phone number. You can also visit the Worldwide Sales Offices page at www.comsol.com/contact/offices for address and contact information.

If you need to contact Support, an online request form is located at the COMSOL Access page at www.comsol.com/support/case.

Other useful links include:

- Support Center: www.comsol.com/support
- Product Download: www.comsol.com/product-download
- Product Updates: www.comsol.com/support/updates
- COMSOL Community: www.comsol.com/community
- Events: www.comsol.com/events
- COMSOL Video Center: www.comsol.com/video
- Support Knowledge Base: www.comsol.com/support/knowledgebase

Part number: CM010004

C o n t e n t s

Before You Begin	1
Installation Media Options.	1
System Requirements	2
Previous Installations	2
Software License Agreement	3
License Types	3
License Management Tools.	5
COMSOL Access.	6
Installing on Windows	7
Installation Over the Internet	7
Installation from Downloaded DVD Image.	11
Installation from a DVD.	12
Installation from a USB Flash Drive	12
Running the COMSOL Installer	13
Removing (Uninstalling) the COMSOL Installation	23
Installing Software Updates.	25
Automated Installation.	25
Product Updates and Model Library Update	26
LiveLink™ for Excel® Installations	27
LiveLink™ for SolidWorks®: Add-In for SolidWorks.	28
LiveLink™ for Inventor®: Add-in for Autodesk Inventor.	28
LiveLink™ for AutoCAD® Installations.	29
LiveLink™ for Pro/ENGINEER®: Changing the Installation Path	29

LiveLink™ for Creo™ Parametric: Changing the Installation Path	30
LiveLink™ for Solid Edge®: Add-in for Solid Edge.....	31
LiveLink™ for SpaceClaim®: Add-in for SpaceClaim.....	31
Cluster Installation	32
License Manager Installation on Windows	33
What is the FlexNet® License Manager?.....	33
System Requirements for the FlexNet® License Manager .	34
FlexNet® License Manager Software Components.....	34
FlexNet® License Manager Documentation.....	34
The License File	35
Installing the License Manager.....	38
Starting the License Manager	40
Verifying that the License Manager is Running.....	41
Starting COMSOL	41
Changing the License.....	42
Troubleshooting License Errors	42
Running COMSOL on Windows.....	43
The COMSOL Folder on The Windows Start Menu	43
Running COMSOL on Windows® 8.....	44
Starting COMSOL for a Classkit License.....	45
Creating Desktop Shortcuts Manually.....	46
Running COMSOL in Client-Server Mode.....	47
Running COMSOL in Batch Mode	49
Running COMSOL on Multicore Computers.....	49

Running COMSOL on Clusters	50
Running COMSOL on the Cloud.	51
Running COMSOL with MATLAB.	52
Installing on Mac OS X.	53
Installation Over the Internet	53
Installation from Downloaded DVD Image.	56
Starting the Installer from DVD or DVD Image.	57
Installation from USB Flash Drive	58
Running The COMSOL Installer.	58
Automated Installation.	59
Removing (Uninstalling) the COMSOL Installation	59
Product Updates and Model Library Update	59
Changing the Path to the MATLAB® Installation.	60
License Manager Installation on Mac OS X.	61
FlexNet License Manager Software Components	61
FlexNet License Manager Documentation	61
The License File	62
Installing the License Manager.	62
Starting the License Manager	62
Verifying that the License Manager is Running	64
Starting COMSOL	64
Changing the License.	64
Troubleshooting License Errors	65
Running COMSOL on Mac OS X	66

The COMSOL Applications	66
Running COMSOL from a Terminal Window	67
Running COMSOL in Client-Server Mode	67
Running COMSOL in Batch Mode	68
Running COMSOL on Multicore Computers	69
Running COMSOL on Clusters	70
Running COMSOL on the Cloud	70
Installing on Linux	71
Installation from Downloaded DVD Image	73
Starting the Installer from Downloaded DVD Image	74
Installation from DVD	74
Installation from USB Flash Drive	75
Running The COMSOL Installer	75
Web Browser for Viewing the Documentation	76
Automated Installation	77
Removing (Uninstalling) the COMSOL Installation	77
Product Updates and Model Library Update	77
Changing the Path to the MATLAB® Installation	78
Cluster Installation	78
License Manager Installation on Linux	80
FlexNet License Manager Software Components	80
FlexNet License Manager Documentation	80
The License File	81
Installing the License Manager	81

Starting the License Manager	82
Verifying that the License Manager is Running	83
Starting COMSOL	84
Changing the License	84
Troubleshooting License Errors	84
Running COMSOL on Linux	85
Running COMSOL	85
Running COMSOL on Multicore Computers	85
Running COMSOL in Batch Mode	86
Running COMSOL in Client-Server Mode	86
Running a Classkit License	88
Running COMSOL on Clusters	88
Running COMSOL on the Cloud	89
Running COMSOL with MATLAB	90
Troubleshooting License Errors	91

Before You Begin

Welcome to the *COMSOL Installation Guide*, which provides instructions on how to install COMSOL Multiphysics® and its add-on products. In addition to this manual, several on-line resources are available which are relevant for installation:

- System Requirements: www.comsol.com/system-requirements
- Support Knowledge Base: www.comsol.com/support/knowledgebase
- Support Center: www.comsol.com/support
- Software License Agreement: www.comsol.com/sla
- Product Download: www.comsol.com/product-download
- Product Updates: www.comsol.com/support/updates
- COMSOL Video Gallery: www.comsol.com/video

Installation Media Options

There are four installation media options for COMSOL 4.4:

- Installation over the Internet:
 - This option requires Internet access from the computer where COMSOL is to be installed.
- Installation from downloaded DVD image:
 - This option requires Internet access from any computer for downloading the DVD image file with a .iso file extension.
- Installation from a DVD given to you by a COMSOL representative:
 - This option requires access to a DVD reader on the computer where COMSOL is to be installed.
- Installation from a USB Flash Drive given to you by a COMSOL representative:
 - This option requires a USB port on the computer where COMSOL is to be installed.

Installation using any of these four options is explained later in this document.

System Requirements

COMSOL is a cross-platform software that runs on the Windows[®], Mac[®], and Linux[®] operating systems. A variety of hardware platforms are supported, including graphics cards. Before installing, make sure your computer meets the current system requirements listed at: www.comsol.com/system-requirements.

There is also a current list of compatible software versions for:

- External function C compiler
- COMSOL API *for use with Java*[®]
- LiveLink[™] *for MATLAB*[®]
- LiveLink[™] *for Excel*[®]
- CAD Import Module
- LiveLink[™] *for SolidWorks*[®]
- LiveLink[™] *for SpaceClaim*[®]
- LiveLink[™] *for Inventor*[®]
- LiveLink[™] *for AutoCAD*[®]
- LiveLink[™] *for Creo*[™] Parametric
- LiveLink[™] *for Pro/ENGINEER*[®]
- LiveLink[™] *for Solid Edge*[®]
- File Import *for CATIA*[®] v5

Previous Installations

Previous installations of COMSOL on your computer are not affected by your new COMSOL 4.4 installation except that double-clicking a Model MPH-file opens in the latest installation (unless otherwise specified during installation). You can continue to use other versions or uninstall them independently of the latest installation.



In this guide, the term COMSOL 4.4 refers not only to COMSOL Multiphysics 4.4 but also to any of the add-on products.

Software License Agreement

For the complete software license agreement with details on the license conditions, please refer to the COMSOL Software License Agreement. The PDF can be downloaded from this link: www.comsol.com/sla. The license agreement is also available in your installation folder. On Windows, it is located at:

```
C:\Program Files\COMSOL\COMSOL44\  
doc\pdf\comsol\COMSOL_SoftwareLicenseAgreement.pdf
```

and can also be accessed from the Windows Start menu, under **COMSOL 4.4>Documentation**.

On Mac, it is located at:


```
/Applications/COMSOL44/doc/pdf/comsol/COMSOL_SoftwareLicenseAgreement.pdf
```

On Linux, it is located in the installation directory, for example:

```
/usr/local/comsol44/doc/pdf/comsol/COMSOL_SoftwareLicenseAgreement.pdf
```

License Types

There is a variety of license options, and the steps involved when installing can differ depending on which license type you have acquired. No license type restricts usage to just one operating system but you are able to choose to install on either Windows, Mac, or Linux. A COMSOL model file saved on one platform can be opened on another. Certain license types come with restrictions; make sure you know which license type you have before proceeding with the installation.

-  All COMSOL licenses allow for multicore/multiprocessor shared-memory computing. How many cores or processors you can utilize is only limited by your hardware configuration and operating system. In the COMSOL Desktop you control the number of processors from the Options menu, under Preferences>Memory and processors.

The picture below summarizes the license types and their usage:

License Type	Multiple Computers	Multiple Platforms	Multiple Users	Client/Server	Clusters	Cloud Computing
NSL	Yes	Yes	No	No	No	No
CPU	No	No	Yes	No	No	No
FNL	Yes	Yes	Yes	Yes	Yes	Yes

NSL

CPU

FNL

All of the license types may not be available in your region.

- !
 For a full description and definition of the different license types, see the *COMSOL Software License Agreement*.

The following summary gives an overview of the different license types:

Named Single User License (NSL)

This license type permits one physical person designated to COMSOL by name to run a session of the software. This designated user can be replaced on a temporary or permanent basis provided that only one individual is designated to COMSOL as the user at any given time. A Named Single User License cannot be used or accessed over a network with tools such as Windows Remote Desktop or similar.

CPU-Locked Single User License (CPU)

This license type permits you to install the software on one computer, and different users can take turns using COMSOL on that computer, one session at a time. A CPU-Locked Single User License cannot be used or accessed over a network with tools such as Windows Remote Desktop or similar.

Floating Network License (FNL)

This license type is intended for multiple users and is licensed per concurrent user. You can install the software on as many computers on your network as you want and these computers can have different operating systems (one being a Windows PC, another running Mac, a third running Linux, and so on).

As a user of a Floating Network License, you can run COMSOL in several ways:

- On your local computer
- On a remote computer accessed over a network

- In Client-Server mode, where you run only the COMSOL Client locally and the COMSOL Server elsewhere on the network, usually on a more powerful computer. The COMSOL Client is essentially the COMSOL Desktop environment whereas the COMSOL Server is the COMSOL computational engine needed for solving.
 - On a cluster or cloud with no restrictions on the number of compute nodes.
- In any of the Floating Network License usage scenarios above, the FlexNet™ license manager software (shipped with COMSOL) needs to be installed and run on a computer somewhere on the network.

Class Kit License

The Class Kit License can be installed and used by up to 30 students including up to two teaching assistants. This type of license is for classroom use only and requires a central license administrator person.

Trial License

This license type can be either a Single User License or Floating Network License with the intention to test the software without any payment obligation for noncommercial and nonproduction use.

License Management Tools

The FlexNet License Manager Software

Depending on your region and operating system, any of the above license types may require that the FlexNet license manager software is installed and started before running COMSOL. The FlexNet license manager comes bundled with any COMSOL installation. You can view the contents of the license file (`license.dat`) that you received from your COMSOL representative by opening it with a text editor or word processing software. If the file contains a line starting with the word `SERVER`, then the FlexNet license manager is required. For a Floating Network License, the purpose of the FlexNet license manager software is to count the number of concurrent users and to give an error message if the number of users exceeds the licensed number of concurrent users. Depending on your region and operating system, the FlexNet license manager software might also be needed for a Single User License. In that case, the purpose of the license manager software is to lock the COMSOL session to a COMSOL authorized computer. See [“License Manager Installation on Windows” on page 33](#) for more information. The COMSOL software products and the license manager can be installed in any

order, except if you are installing based on a port number and host name. In that case, the license manager software needs to be installed and started before installing COMSOL.

Dongle Hardware Lock

Depending on your region and operating system, any of the above license types might require a dongle (hardware lock). If you have received a dongle to use with COMSOL, please refer to instructions given to you by your COMSOL representative.

COMSOL Access

COMSOL Access is a service provided by COMSOL that gives you access to additional content on www.comsol.com and allows you to:

- Download products
- Update products (restricted to customers with an active subscription)
- Edit contact and license information
- Access the Knowledge Base (unabridged access to all parts is restricted to customers with an active subscription)
- Contact technical support
- Manage event registrations
- Manage abstract submissions to the COMSOL Conference
- Access to the COMSOL Exchange on-line model sharing
- Participate in the Community Discussion Forum

Registering with COMSOL Access is required for product download and installation.

Installing on Windows

Installation Over the Internet

INSTALLATION OF A TRIAL LICENSE OVER THE INTERNET

A trial license can be given to you with the intention to test the software without any payment obligation for noncommercial and nonproduction use. This option is not available in all regions.

Installation of a Single User Trial License on Windows requires a license passcode. A passcode has a form similar to:

FFFFFFFF - TYUS - 123456 - 1234567 - 123456789

This is usually sent to you by a COMSOL representative by email. Once you locate your passcode, follow these steps to prepare for download and installation:

- 1 Click the link for downloading the software as given in the software download email from your COMSOL representative. This link is identical or similar to: www.comsol.com/support/download/trial.
- 2 If you haven't already created a COMSOL Access account, you will be prompted to create it. While creating the account, enter your trial passcode to associate it with your account information.

If you already have created a COMSOL Access account, then the link www.comsol.com/support/download/trial directs you to a page where you can enter the passcode:

- 3 Follow the web-based instructions to download the software.
- 4 Continue with the instructions in the section “[Downloading the COMSOL Installer](#)” on page 10.

INSTALLATION OF A PAID-FOR LICENSE OVER THE INTERNET

Installation of any paid-for license on Windows requires a license file that is sent to you by your COMSOL representative by email. To be able to generate the license file, information about your hardware is needed in the form of a hostid (host ID). The hostid is used to lock the license to your hardware and needs to be sent by you to a COMSOL representative prior to the license file being generated.

Obtaining the Hostid

Follow these steps to obtain a hostid:

- 1 First open the command window by pressing the keyboard Window button+R. If you don't have a Window button, click the **Start** button, enter `cmd` in the search box, and press OK or Return.
- 2 Enter `ipconfig /all` at the command prompt and press Return. The displayed information looks similar to this:

```
Administrator: C:\Windows\system32\cmd.exe
Microsoft Windows [Version 6.0.6001]
Copyright (c) 2006 Microsoft Corporation. All rights reserved.

C:\Users\Paul>ipconfig/all

Windows IP Configuration

Host Name . . . . . Pauls-PC
Primary Dns Suffix . . . . . acme.com
Node Type . . . . . Hybrid
IP Routing Enabled. . . . . No
WINS Proxy Enabled. . . . . No
DNS Suffix Search List. . . . . acme.com

Ethernet adapter Local Area Connection:

Connection-specific DNS Suffix . : acme.com
Description . . . . . Broadcom NetXtreme 57xx Gigabit Controller
Physical Address. . . . . 00-1E-C9-34-BD-CB
DHCP Enabled. . . . . Yes
Autoconfiguration Enabled . . . . . Yes
Link-local IPv6 Address . . . . . fe80::c09a:789a:5936:6b30%9(Preferred)
IPv4 Address. . . . . 10.0.1.49(Preferred)
Subnet Mask . . . . . 255.255.0.0
Lease Obtained. . . . . Tuesday, September 23, 2008 09:49:45
Lease Expires . . . . . Thursday, September 25, 2008 12:26:42
Default Gateway . . . . . 10.0.0.1
DHCP Server . . . . . 10.0.0.25
DNS Servers . . . . . 10.0.0.1
NetBIOS over Tcpip. . . . . Enabled

C:\Users\Paul>
```

- 3 The hostid you are looking for is here called Physical Address, also known as Ethernet address or MAC address.

To place the number on the Windows clipboard, right-click the text in the command window and select **Mark** in the menu, mark with the mouse, and press Return. Alternatively, you can type the command:

```
getmac /FO LIST /V | clip
```

which also places the information on the Windows clipboard.

- 4 Now press Ctrl+V to paste the hostid to the text body of an email to be sent to a COMSOL representative.

Obtaining the Host Name

If you have been informed by your COMSOL representative that you need to run the FlexNet license manager for your installation, then you also need the Host Name. The Host Name is encircled in the screen shot above. If your network administrator prefers to use a fixed IP address for this particular computer, this IP Address can be optionally used in place of the Host Name. For more information

on license manager installation see “[License Manager Installation on Windows](#)” on page 33.

Hostid for PCs with Wireless Adapters

If you plan to install on a computer with a wireless network adapter, you need the physical address of both the wireless and the Ethernet adapter. If the COMSOL representative asks you for the hard disk serial number instead of the hostid, type `vol` at the Windows command line prompt. The output looks like

```
Volume Serial Number is 2C9F-5930
```

Obtaining the License File from a COMSOL Representative

Send the hostid information, as well as Host Name, if applicable, in an email to your COMSOL representative, who will respond with an email with an attached license file (`license.dat`). Save this file to any location on your computer. You need to refer to it during installation. The license file is a text file and below is an example of the contents of a `license.dat` file for a Single User License on Windows. This example license file shows that the licensed products are COMSOL Multiphysics, Particle Tracing Module, Subsurface Flow Module, and LiveLink™ for Excel®.

```
#-----  
# COMSOL 4.4 NSL License No: 1234567 Windows/Mac  
# Visit www.comsol.com/install for latest installation instructions  
#-----  
FEATURE SERIAL LMCOMSOL 4.32 permanent uncoun ted \  
    VENDOR_STRING=C,18000100200 HOSTID=ANY sort=100 SN=1234567 \  
    TS_OK SIGN=8045890A6FE4  
FEATURE COMSOL LMCOMSOL 4.32 permanent uncoun ted HOSTID="70f2b12f4dfd \  
    0116b8cc761a" PLATFORMS="i86_n x64_n i86_mac x64_mac" \  
    SN=2076312 SIGN=E607EB680852  
FEATURE PARTICLETRACING LMCOMSOL 4.32 permanent uncoun ted \  
    HOSTID="70f1a12f4dfc 0026b9cc760a" PLATFORMS="i86_n x64_n \  
    i86_mac x64_mac" SN=2076312 SIGN=3835733C6290  
FEATURE SUBSURFACEFLOW LMCOMSOL 4.32 permanent uncoun ted \  
    HOSTID="70f1a12f4dfc 0026b9cc760a" PLATFORMS="i86_n x64_n \  
    i86_mac x64_mac" SN=2076312 SIGN=3A9BA162C9E4  
FEATURE LLEXCEL LMCOMSOL 4.32 permanent uncoun ted HOSTID="70f1a12f4dfc \  
    0026b9cc760a" PLATFORMS="i86_n x64_n i86_mac x64_mac" \  
    SN=2076312 SIGN=EE9C11E44356  
FEATURE COMSOLGUI LMCOMSOL 4.32 permanent uncoun ted \  
    HOSTID="70f1a12f4dfc 0026b9cc760a" PLATFORMS="i86_n x64_n \  
    i86_mac x64_mac" SN=2076312 SIGN=0D0A83382550
```

A Single User License file can normally not be edited or changed in any way by the user but has to be identical to the one sent to you by a COMSOL representative. If you were sent a license file that requires a license manager, then minor edits are required. For information on the type of license file required for installations using a license manager, see “[The License File](#)” on page 35.


Registering with COMSOL Access

Once you have saved your license file, follow these steps to register or login to COMSOL Access to start the installation:

- 1 Click the link for downloading the software as given in the software download email from your COMSOL representative. This link is identical or similar to: www.comsol.com/product-download.
- 2 If you haven't already created a COMSOL Access account, you will be prompted to create it. While creating the account, point to your license file (`license.dat`) to associate it with your account information.

If you already created a COMSOL Access account, then you can associate the license file with your account on the COMSOL Access page under Manage Licenses at www.comsol.com/access/licenses
- 3 Continue with the instructions in the next section.

DOWNLOADING THE COMSOL INSTALLER

- 1 Go to the web page www.comsol.com/product-download.
 - 2 You are now given the option of installing COMSOL using the **Online Installer**. (For the DVD option see “Installation from Downloaded DVD Image” on [page 11](#).) In addition, there are two further options of Compact Installation or Full Installation:
 - **Compact Installation:** Includes the on-line documentation. The model library tutorials are stripped of solutions, which reduces download time. The size of this download ranges from 600 MB to 1.6 GB depending on your license.
 - **Full Installation:** Includes the full documentation and the complete model library with meshes and solutions for your licensed products. The size of this download ranges from 1.0 GB to 3.7 GB depending on your license.
-  If you have problems downloading (such as **Error downloading file. Connection refused: connect**), please review this knowledge base entry: www.comsol.com/support/knowledgebase/1149. If you still have problems, please contact your local COMSOL representative or technical support from the Support Center page at www.comsol.com/support.
- Selection one of the options for Compact Installation or Full Installation.

Clicking one of the install buttons starts the download of the COMSOL Installer. For Windows, the file to download is called `COMSOL44_win.exe` for the Full Installation and `COMSOL44_compact_win.exe` for the Compact Installation.


STARTING THE INSTALLER FOR INSTALLATION OVER THE INTERNET

The COMSOL Installer is a user interface tool that guides you through the installation process. Start the COMSOL Installer by running one of the downloaded files `COMSOL44_win.exe` or `COMSOL44_compact_win.exe`, corresponding to the full and compact version, respectively. The COMSOL 4.4 Installer window should now appear. Now continue with the instructions in the section “[Running the COMSOL Installer](#)” on page 13.

Installation from Downloaded DVD Image

Installation from a DVD where the DVD image is downloaded from COMSOL for off-line installation requires you to first create a COMSOL Access account as described in the section “[Installation Over the Internet](#)” on page 7.

- 1 Once you are logged in to COMSOL Access, you are now given the option of installing COMSOL using the **Online Installer** or to download the **DVD Image for Offline Installation**. This section covers the DVD Image option. In addition, there are two further options of Compact Installation or Full Installation:
 - **Compact Installation:** Includes the on-line documentation. The model library tutorials are stripped of solutions, which reduces download time. The size of this download ranges from 600 MB to 1.6 GB depending on your license.
 - **Full Installation:** Includes the full documentation and the complete model library with meshes and solutions for your licensed products. The size of this download ranges from 1.0 GB to 3.7 GB depending on your license.

 If you have problems downloading (such as **Error downloading file. Connection refused: connect**), please review this knowledge base entry: www.comsol.com/support/knowledgebase/1149. If you still have problems, please contact your local COMSOL representative or technical support from the Support Center page at www.comsol.com/support.
- 2 In the section for the DVD Image option, click one of the buttons for **Compact DVD Download** or **Full DVD Download**. Clicking one of the install buttons starts the download of the COMSOL DVD Image. The file to download is called `COMSOL44_dvd.iso`.
- 3 When you have downloaded the DVD image, burn the DVD image to a disc to be able to install. In Windows 7 and Windows 8 you can burn by right-clicking on the DVD image and selecting **Open with** and then **Windows Disc Image Burner**. For earlier Windows versions you need a dedicated DVD burning software to use this option. In Windows 8 you have the additional option of directly

mounting the DVD image by right-clicking on the DVD image and selecting **Mount** and then continuing directly with the installation. For earlier Windows versions, you can use a dedicated DVD image mounting software to circumvent burning to DVD.

STARTING THE INSTALLER FROM A DVD OR MOUNTED DVD IMAGE

The COMSOL Installer is a user interface tool that guides you through the installation process. Once you have inserted the COMSOL DVD into the DVD drive (or mounted the image), the COMSOL Installer window should appear automatically; if not, run the file `setup.exe` on the installation DVD. The COMSOL 4.4 Installer window should now appear. Now continue with the instructions in the section [“Running the COMSOL Installer” on page 13](#).

Installation from a DVD

This section applies if you have received a DVD from a COMSOL representative.

STARTING THE INSTALLER FROM A DVD

The COMSOL Installer is a user interface tool that guides you through the installation process. Insert the COMSOL DVD into the DVD drive on your computer. The COMSOL Installer window should appear automatically; if not, run the file `setup.exe` on the installation DVD. The COMSOL 4.4 Installer window should now appear. Now continue with the instructions in the section [“Running the COMSOL Installer” on page 13](#).

Installation from a USB Flash Drive

This section applies if you have received a USB Flash Drive from a COMSOL representative.

STARTING THE INSTALLER FROM A USB FLASH DRIVE

The COMSOL Installer is a user interface tool that guides you through the installation process. Insert the USB Flash Drive into a USB port on your computer. The COMSOL Installer window should appear automatically; if not,

run the file `setup.exe` on the USB Flash Drive. The COMSOL 4.4 Installer window should now appear. Now continue with the instructions in the section “[Running the COMSOL Installer](#)” on page 13 below.

Running the COMSOL Installer


The steps for running the COMSOL Installer are independent of the installation media option you used. If you have followed the above instructions, the COMSOL Installer should now appear. The procedure is the same for Mac OS X with the following exceptions:




COMSOL does not work if the path to the COMSOL folder, or the name of the COMSOL folder itself, contain spaces.

You cannot browse to the MATLAB installation directory directly. You need to enter it manually. MATLAB is installed in the `/Applications` directory, for example, as `/Applications/MATLAB_R2013b.app`.

1 Select your language for the installation and click **Next**. The language you select will also become your default language in COMSOL.






- 2 In the COMSOL Installer, select one of the following options:
- Click **New COMSOL 4.4 Installation** and proceed to Step 3 (License Page) to make a new installation.
 - Click **Add/Remove Features and Repair** and proceed to Step 5 (Platform Page) to change or repair an existing installation. For example, use Add/Remove Features and Repair when adding or removing documentation files for products installed or when adding or removing a product that your license includes.
 - Click **Change License** and proceed to Step 3 (License Page) to update the license of an existing installation. Use this option when COMSOL is installed and you get a new license file. The installer then removes features/products not licensed any more and lets you go through the Add/Remove Features procedure to add or remove features for the new license. If your trial license has expired you can use the Change License option to re-enable a paid-for license.
 - Click **Uninstall COMSOL 4.4** to remove an existing installation. For instructions on this option, proceed to [“Removing \(Uninstalling\) the COMSOL Installation”](#) on page 23.



You can change the path to the existing installation by pressing the F1 key.

LICENSE PAGE

3 After selecting one of the four options, the following is displayed:



After reading the license agreement, click the **I accept the terms of the license agreement** button and specify the license. Use one of the following license formats, depending on which license you have:


- **Passcode:** Use this option for a Single-User Trial License. Enter your passcode, which is a series of characters and numbers that has a form similar to FFFFFFFFFFFFFF-TYUS-123456-1234567-123456789. Note that the passcode is case sensitive.
- **License file:** Use this option for any type of regular paid-for license installation. Enter the path to an existing license file or click **Browse** to select the file license.dat. This license file is sent to you by a COMSOL representative, typically by email.
- **Port number and Host Name:** Use this option if your license administrator has given you a port number and Host Name for a license manager for COMSOL that is running somewhere on your organization's network. Enter the **Host**

Name of the computer or server running the license manager and its license manager port number.

- **Three-server redundancy:** Use this option if your license administrator has given you three port numbers and Host Names for the three-server redundancy license manager option. Enter the **Host Names** and license server port numbers of the three-server redundant configuration.

Change License

If **Change License** was selected in Step 2, a menu in the upper-left area of the Installer lets you choose to use an existing paid license, trial license, or you can choose to specify a new license.




Click **Next** and proceed to Step 5 if you want to change to a license with different products. Otherwise, proceed to Step 10.

4 Click **Next**.

PLATFORMS PAGE

5 On the **Platforms** page, you can typically accept the default settings. COMSOL autodetects the type of operating system, which, for installation on Windows,


can be Windows 32-bit or Windows 64-bit. On the 64-bit version of Windows you can choose to install both versions.








6 Click **Next**.


FEATURES PAGE

7 Select the features to install and specify the path to the COMSOL installation folder.



Feature symbols:

-  — not currently installed, will be installed
-  — not currently installed, will not be installed
-  — currently installed, will not be updated
-  — currently installed, will be updated
-  — currently installed, will be removed


 If **Change License** was selected earlier and you are changing the license of an already existing installation, you need to pay attention to which check boxes are selected. If you are adding products not previously part of your installation, but added with the new license file, then you need to verify the selection of the check boxes for the corresponding installation components. (If you don't, the license information is still correct but the software components needed to run the products will be missing.)

Add/Remove Features

If **Add/Remove Features** or **Change License** was selected in Step 2, the Features page includes a **Repair all selected features** check box. If this check box is selected, the selected set of features determines which software components, documentation, and models are to be added or removed. Features that are selected are added if not previously installed, and features that are not selected are removed if previously installed. The selected set only affects those products that you have licensed.

8 Click **Next**.

OPTIONS PAGE



9 Set the installation options:

- Create COMSOL shortcuts on Windows Desktop
- Create COMSOL folder in the Windows Start Menu
- Associate the .mph file type with this COMSOL installation

If this check box is selected, you can open COMSOL models by double-clicking them.

- Install Microsoft DirectX® runtime binaries

Clear the Install DirectX runtime binaries check box if you previously experienced problems using DirectX on your computer. DirectX can be used

by COMSOL for accelerated graphics rendering. If you clear this check box, then you still have two graphics options: OpenGL or software rendering. Once installation is complete, you can change the graphics rendering method from the Preferences dialog box on the Options menu in the COMSOL Desktop.




For a Floating Network License, you can access COMSOL with a Windows Remote Desktop connection. This way of accessing COMSOL is only supported with the software rendering graphics option.

- Check for updates after installation. This option is selected by default. The installer then checks and applies all updates that are available for the version that you install.
- Enable automatic updates after installation. Select this check box if you want COMSOL to automatically check for and apply available software updates.
- Install LiveLink™ *for* Excel® for all users. If you select this check box, the installation of LiveLink™ *for* Excel® is global to the machine and is available no matter which user is logged on. Otherwise, the installation is only available to the current user (this is the only supported option for Excel 2007).
- If you install over the Internet using a proxy server, you can specify the host name, port number, and, optionally, a username and password if required. If you do not enter a port number, COMSOL uses port 443, which is the default port setting for the HTTPS protocol. These settings do not appear if you do not perform an installation via the Internet.
- For the LiveLink™ products *for* MATLAB®, Pro/ENGINEER®, and Creo Parametric®, specify the path to their respective installation folders.

10 Click **Next**.


INSTALL PAGE



II When you click **Install** the utility now installs or updates COMSOL. The installation process might take several minutes. A full installation including all products typically takes more than 15 minutes to complete. If you are installing over the internet, the installation time will depend on your internet connection speed. The Finish page in Step 12 appears automatically when the installation process is finished.

FINISH PAGE

12 This window appears when the installation is finished.



If warning or errors were detected, click **View Log** to open a window that shows the installation log. Do not hesitate to contact technical support if you encountered any errors and remember to send the installation log file along with your technical support inquiry.

13 Click **Finish** to quit the installer.

For information on how to run COMSOL after installation, see [“Running COMSOL on Windows”](#) on page 43. If you are installing on a Mac, see [“Running COMSOL on Mac OS X”](#) on page 66. If you are installing on Linux, see [“Running COMSOL on Linux”](#) on page 85.


Removing (Uninstalling) the COMSOL Installation


To remove a COMSOL installation from your system, you can uninstall using the COMSOL Installer’s uninstallation option. The uninstaller deletes all old version

COMSOL files and directories on the system that were installed by the COMSOL installer. Additional files and folders created after installation are not removed.

If COMSOL is run with MATLAB, close MATLAB before starting the uninstaller. If MATLAB is active, the utility cannot remove certain files.


You can start the COMSOL Uninstaller in a few different ways:

- From the Windows Start Menu, open the **Control Panel** and select **Uninstall a program**. Find COMSOL 4.4 in the list and select **Uninstall**.
- From the Windows Start Menu under COMSOL 4.4, select **Uninstall COMSOL Multiphysics 4.4**.
- Insert the COMSOL DVD and start the COMSOL Uninstaller. Click **Uninstall COMSOL 4.4**  to start removing the installation. Click **Finish** to quit the installer when the uninstallation is complete.
- In Windows 8, go to the **All apps** page and click the COMSOL Launchers folder. In that folder you find the Uninstaller.



Installing Software Updates

COMSOL provides software updates that improve the software and correct issues. To check if an update is available, choose **Check For Updates** from the **Help** menu. If an update is available, an **Update** dialog box appears. Click **Download** to download the update directly, or click **Browse Update** to open the COMSOL website where you can read about and download the update. To check for updates automatically each time you start COMSOL, select the **Check for updates at launch** check box under **Product updates** on the **Updates** page in the **Preferences** dialog box. When the update installation starts (close any running instance of COMSOL) you see the following installation window:



You can use a direct download (the default) or download via a proxy server. If you download via a proxy server, specify the host name and port number for the proxy and, if required, a username and password.

Automated Installation

You can install COMSOL using an automated installation process with minimal user interaction. This method requires installation from a DVD or DVD image.

An answer file then responds to questions while the installer is running. The answer file is a text file with a specific format that contains predefined settings that the COMSOL installer uses. Start the installation by running

```
<path to DVD>\setup.exe -s <answer file path>
```

where *<answer file path>* is the path to your answer file. A template answer file, `setupconfig.ini`, with detailed usage information is available on the DVD.

AUTOMATED REMOVAL (UNINSTALLATION) OF COMSOL

You can uninstall COMSOL using an answer file:

```
<path to COMSOL>\setup\setuplauncher.exe -s <answer file path>
```


where *<answer file path>* is the path to your answer file.

Product Updates and Model Library Update

COMSOL periodically releases product updates with improvements and corrections to reported problems. By default, COMSOL checks for updates at startup. You can turn this feature on and off from the COMSOL Desktop Preferences window. Here you can also configure settings for the Model Library Update.

The COMSOL Model Library is updated on a regular basis by COMSOL. To open the Model Library Update window from the File>Help menu (Windows users) or from the Help menu (Mac and Linux users), select Update COMSOL Model Library.

This connects you to the COMSOL Model Library Update website where you can access the latest models and model updates. This includes models that have been added or improved since the latest product release.



Using the **Updates** section in the **Preferences** dialog box you can configure proxy server settings as well as model and documentation directories for the Model Library Update. See the *COMSOL Multiphysics Reference Manual* for more information, including command-line options for the Model Libraries.

LiveLink™ for Excel® Installations

If you have licensed LiveLink™ for Excel®, several tools are accessible from a COMSOL tab in the Excel ribbon for working with a COMSOL model from an Excel worksheet. You can, for example, extract model definitions and results. You can also change model definitions in the worksheet, then update and re-compute the model.

Whenever you open a COMSOL model from Excel, a COMSOL Server is started where the model is loaded. The data transfer between Excel and the COMSOL Server application is performed using a TCP/IP communication protocol, which accepts only local connections.

LiveLink™ for SolidWorks®: Add-In for SolidWorks

If you have licensed LiveLink™ for SolidWorks®, the COMSOL Installer registers an add-in called the LiveLink for COMSOL (4.4). This add-in should appear in the SolidWorks user interface, listed in the Add-Ins dialog box, accessible from the Tools menu.

The add-in provides tools for preparing your SolidWorks design for simulation with COMSOL. For example, you can create selections on the geometry and set up dimensional parameters. Those selections and parameters, together with the geometry, are synchronized with the COMSOL model.

The add-in enables two modes of setting up simulations based on the SolidWorks design:

- In one mode you can run SolidWorks and the COMSOL Desktop side-by-side and synchronize the geometry between the two.
- In another mode you can work with COMSOL simulations inside SolidWorks. This latter mode is called the One-Window interface. Only one version of the One-Window interface can be active at a time. If you have several COMSOL versions installed, make sure that the latest version of LiveLink for COMSOL is selected from the **COMSOL>One-Window Version** menu inside SolidWorks. If required, restart SolidWorks after changing the One-Window interface version.

If COMSOL cannot connect to SolidWorks, you can re-install COMSOL, or follow the instructions from the following link:

<http://www.comsol.com/support/knowledgebase/1122>.

LiveLink™ for Inventor®: Add-in for Autodesk Inventor

If you have licensed LiveLink™ for Inventor®, the installer registers an add-in for Autodesk Inventor called the LiveLink for COMSOL (4.4). This add-in should

appear in the Add-In Manager dialog box that is accessible from the Options tab of the Tools panel in the Autodesk Inventor user interface.

The add-in provides tools for preparing your Inventor design for simulation with COMSOL. For example, you can set up dimensional parameters that, together with the geometry, are synchronized with the COMSOL model.

The add-in enables two modes of setting up simulations based on the Inventor design:

- In one mode you can run Inventor and the COMSOL Desktop side-by-side and synchronize the geometry between the two.
- In another mode you can work with COMSOL simulations inside Inventor. This latter mode is called the One-Window interface.

If COMSOL cannot connect to Inventor, you can re-install COMSOL, or follow the instructions from the following link:

<http://www.comsol.com/support/knowledgebase/1163>.

LiveLink™ for AutoCAD® Installations

If you have licensed LiveLink™ for AutoCAD®, the installer registers an add-in with AutoCAD called LiveLink for COMSOL (4.4). This add-in is loaded on start-up of AutoCAD and provides functionality for synchronizing the geometry between AutoCAD and COMSOL.

If you install a newer version of AutoCAD, and can no longer establish a connection between the software, you can re-install COMSOL to register the add-in with this new version of AutoCAD.

LiveLink™ for Pro/ENGINEER®: Changing the Installation Path

If you have licensed LiveLink™ for Pro/ENGINEER®, you need to provide the installation path for Pro/ENGINEER or Creo Elements/Pro during the install process. The installer registers an add-in with Pro/ENGINEER called LiveLink for COMSOL (4.4). The add-in should be listed in the Auxiliary Applications dialog box that is accessible from the Tools menu in the Pro/ENGINEER user

interface. The add-in provides functionality for selecting dimensional parameters that can be synchronized with COMSOL.

After the installation you can configure the interface to work with a different Pro/ENGINEER installation. Go to the Preferences window, which you can access from the Options menu inside the COMSOL Desktop. There find the LiveLink products section and edit the Pro/ENGINEER installation folder. It should point to the root directory of the Pro/ENGINEER installation, typically

`C:\Program Files\proeWildfire 5.0`

or, for an installation of Creo Elements/Pro,

`C:\Program Files\PTC\Creo Elements\Pro5.0`

If you have installed both LiveLink for Pro/ENGINEER and LiveLink for Creo Parametric, you can use only one of those during a COMSOL Multiphysics modeling session. The default is to connect to Creo Parametric. To connect to Pro/ENGINEER select LiveLink for Pro/ENGINEER from the Use list.

Restart COMSOL for the changes to take effect.

Note that changing the Pro/ENGINEER installation folder in the Preferences window does not re-register the add-in with that Pro/ENGINEER installation. To do this you can reinstall COMSOL, or follow the instructions from the following links “Parameter Selection is not available in the Pro/ENGINEER user interface”:

<http://www.comsol.com/support/knowledgebase/1159>

If COMSOL cannot connect to Pro/ENGINEER Wildfire 4.0, follow the instructions from the following link:

<http://www.comsol.com/support/knowledgebase/1162>

LiveLink™ for Creo™ Parametric: Changing the Installation Path

If you have licensed LiveLink™ for Creo™ Parametric, you need to provide the path to the common files folder in the Creo Parametric installation during the installation process. After the installation you can configure the interface to work with a different Creo Parametric installation. To do so, go to the Preferences window, which you can access from the Options menu inside the COMSOL Desktop. There find the LiveLink products section and edit the Creo Parametric common files folder. It should point to the common files directory of the Creo Parametric installation, typically

C:\Program Files\PTC\Creo 2.0\Common Files\M040

Restart COMSOL for the changes to take effect.

Note that changing the Creo Parametric common files folder in the Preferences window does not re-register the add-in with that Creo Parametric installation. To do this you can re-install COMSOL, or follow the instructions from the following link:

<http://www.comsol.com/support/knowledgebase/1158>.

LiveLink™ for Solid Edge®: Add-in for Solid Edge

If you have licensed LiveLink™ for Solid Edge®, the installer creates an add-in to Solid Edge called LiveLink for COMSOL (4.4). This add-in should appear in the Add-In Manager dialog box that is accessible in the Solid Edge user interface if you click the Applications button, then select Add-Ins from the menu.

When the add-in is active a COMSOL Multiphysics tab appears in Solid Edge. Use the Parameter Selection tool from the tab to select dimensional parameters that, together with the geometry, are synchronized between Solid Edge and COMSOL.

If COMSOL cannot connect to Solid Edge, you can re-install COMSOL, or follow the instructions from the following link “Error: Failed to connect to Solid Edge”:

<http://www.comsol.com/support/knowledgebase/1160>

LiveLink™ for SpaceClaim®: Add-in for SpaceClaim

If you have licensed LiveLink™ for SpaceClaim®, the installer registers an add-in with SpaceClaim called LiveLink for COMSOL (4.4). This add-in should appear in the Add-Ins section of the SpaceClaim Options dialog box that is accessible in the SpaceClaim user interface if you click the button for the Applications menu.

When the add-in is active you synchronize the geometry and any driving dimensions that are defined on the geometry between SpaceClaim and COMSOL.

If COMSOL cannot connect to SpaceClaim, you can reinstall COMSOL, or follow the instructions from the following link “Error: Failed to connect to SpaceClaim”:

Cluster Installation

COMSOL supports two mutual modes of parallel operation: shared-memory parallel operations and distributed-memory parallel operations, including cluster support. This section is dedicated to distributed-memory parallel installation.

COMSOL can distribute computations on compute clusters using the MPI model. One large problem can be distributed across many compute nodes. Also, parametric sweeps can be distributed with individual parameter cases distributed to each cluster node.

LICENSE MANAGER

COMSOL requires a Floating Network License for running on clusters. Please check the license file for the CLUSTERNODE feature, which needs to be present to enable the cluster computing functionality. The license manager needs to be accessible from all nodes in the cluster. Therefore it is often a good idea to have it run on the head node.

INSTALLATION FOLDER

The COMSOL installation folder should be shared between all compute nodes and the head node.

FEATURES

During installation, make sure the Cluster Components feature is selected.

ACCESS TO CLUSTER (WINDOWS HPC SERVER ONLY)

If you work on a desktop PC, install COMSOL on that PC. Before you start, you need to install Windows HPC Pack on the PC. This software is free and shipped with the Windows Server operating system and enables you to access the cluster from your PC.

For more information on installing and running COMSOL on clusters, see [“Running COMSOL on Clusters”](#) on page 50 and the *COMSOL Multiphysics Reference Manual*.

License Manager Installation on Windows

Depending on your region and operating system, you might be required to install and run the FlexNet license manager software in order to run COMSOL.

What is the FlexNet® License Manager?

COMSOL uses the FlexNet license manager version 11 from Flexera Software, Inc. for license management. (FlexNet was formerly called FLEXlm™.)

The license manager comes bundled with any COMSOL installation. The COMSOL software products and the license manager can be installed in any order, unless you are installing based on a port number and Host Name. In that case, the license manager software needs to be installed and started before installing COMSOL.

Installation of any paid-for license on Windows requires a license file (`license.dat`), which is sent to you by a COMSOL representative by email. You can view the contents of the license file by opening it with a text editor or word processing software. If the file contains a line starting with the word `SERVER`, then the FlexNet license manager is required. For a Floating Network License, the purpose of the license manager software is to count the number of concurrent users and to give an error message if the number exceeds the licensed number of concurrent users. Depending on your region and operating system, the license manager software might also be needed for Single User Licenses. In that case, the purpose of the license manager software is to lock a COMSOL session to a computer that is authorized by COMSOL.

The FlexNet license manager supports a heterogeneous network of Windows, Linux, and Mac OS X computers. Both the license manager and the COMSOL software can run on either Windows, Linux, or Mac platforms. In this context, the computer where the license manager is installed is called the license server and any computer that has the COMSOL products installed is called a client. Any type of computer can function as a license server, such as a laptop, desktop, workstation or a centrally located server. COMSOL can be installed anywhere, typically on a local PC or on a file server where users access the program over a network. A single computer can function as both license server and client, holding both the license manager and COMSOL.

Even though the license manager and COMSOL can be installed in any order, a full test of the installation cannot be done until both are installed.

System Requirements for the FlexNet® License Manager

Before starting the installation process, check that your system meets all necessary requirements as listed at: www.comsol.com/system-requirements. For COMSOL, all requirements need to be met. If you are running the license manager on a license server where you did not intend to run COMSOL, the system requirements are less stringent. The license server only needs to meet the listed hardware and operating system requirements. For the license manager, memory and graphics requirements do not need to be met. The license manager is a much less CPU- and memory-demanding application than COMSOL.


FlexNet® License Manager Software Components

The license manager consists of four software components:

- License manager daemon (`lmgrd.exe`)
- Vendor daemon (`LMCOMSOL.exe`)
- FlexNet utility program (`lmutil.exe`)
- FlexNet Control Panel (`lmtools.exe`)

The two daemons (`lmgrd.exe` and `LMCOMSOL.exe`) run on the license server. When a user starts COMSOL on a client computer, communication is established through the network from the client to the license server and the license manager daemon (`lmgrd.exe`). That daemon in turn makes a request to the vendor daemon (`LMCOMSOL.exe`), which releases licenses according to information in the `license.dat` file. The FlexNet utility program and FlexNet Control Panel are used for handling license server management tasks.

FlexNet® License Manager Documentation

For detailed information on the FlexNet license manager software, click the  button and choose Help>Documentation (Windows) or select Help>Documentation (Mac and Linux). Then scroll to the bottom of the page to locate a PDF copy of the *FlexNet License Administration Guide* for FlexNet Publisher. You can also find the FlexNet documentation on your hard drive. The

default folder location is C:\Program
Files\COMSOL\COMSOL44\doc\pdf\comsol\flexnet

The License File

The license file has the same structure on all platforms: Windows, Mac OS X, and Linux. In this section, the most important parts of the license file are explained. Below is an example of the contents of a `license.dat` file:

```
#-----  
# COMSOL 4.4 FNL License No: 1234567  
# Visit www.comsol.com/install for latest installation instructions  
#-----  
SERVER apollo.thecompany.com 0050569e1b87 1718  
USE_SERVER  
VENDOR LMCOMSOL port=1719  
FEATURE SERIAL LMCOMSOL 4.32 permanent uncounted \  
    VENDOR_STRING=C,5701108 HOSTID=ANY BORROW=720 SN=1234567 TS_OK \  
    SIGN=0C3A8BF6722E  
INCREMENT COMSOL LMCOMSOL 4.32 permanent 4 SUPERSEDE DUP_GROUP=UHD \  
    ISSUED=6-JUN-2012 BORROW=720 SN=1234567 SIGN=123456789ABC  
INCREMENT COMSOLGUI LMCOMSOL 4.32 permanent 4 SUPERSEDE DUP_GROUP=UHD \  
    ISSUED=6-JUN-2012 BORROW=720 SN=1234567 SIGN=123456789ABC  
INCREMENT HEATTRANSFER LMCOMSOL 4.32 permanent 2 SUPERSEDE \  
    DUP_GROUP=UHD ISSUED=6-JUN-2012 BORROW=720 SN=1234567 \  
    SIGN=123456789ABC  
INCREMENT CLIENTSERVER LMCOMSOL 4.32 permanent 4 SUPERSEDE \  
    DUP_GROUP=UHD ISSUED=6-JUN-2012 BORROW=720 SN=1234567 \  
    SIGN=123456789ABC  
INCREMENT CLUSTERNODE LMCOMSOL 4.32 permanent 4 SUPERSEDE DUP_GROUP=U \  
    ISSUED=6-JUN-2012 BORROW=720 SN=1234567 SIGN=123456789ABC  
INCREMENT COMSOLBATCH LMCOMSOL 4.32 permanent 2 SUPERSEDE \  
    DUP_GROUP=UHD ISSUED=6-JUN-2012 BORROW=720 SN=1234567 \  
    SIGN=123456789ABC  
INCREMENT HEATTRANSFERBATCH LMCOMSOL 4.32 permanent 2 SUPERSEDE \  
    DUP_GROUP=UHD ISSUED=6-JUN-2012 BORROW=720 SN=1234567 \  
    SIGN=123456789ABC
```

THE COMMENT LINES

Comment lines can be included in the license file by starting them with the hash symbol `#`. These lines have no effect on the license server or client.

THE SERVER LINE

In the `license.dat` file, the contents of the line starting with `SERVER` should contain:

- The Host Name of the license server. In the example above, the Host Name is `apollo.thecompany.com`. This name can be edited by the user.
- The `hostid` of the license server. In the example above, the `hostid` is `0050569e1b87`. This number cannot be edited by the user.
- A port number. In the example above, the port number is `1718`. This number can be edited by the user.

Confirm that the license server Host Name is the actual name of your license server (the computer that you intend to run the FlexNet license manager software on); otherwise, change it by editing the file. The default port number (`1718`) can be changed in the unlikely event that another program is already using that port number (you then get an error message indicating this when starting the license manager). If the default port number `1718` is being used, change it to any other number between `1025` and `64,000`.

THE USE_SERVER LINE

The `USE_SERVER` line, with no arguments, does not impact the license manager but has implications for the client. When a COMSOL client sees the `USE_SERVER` line, it ignores everything in the license file except the preceding `SERVER` lines and transfers checkout validation to the vendor daemon. This means that if you are running COMSOL on one computer, and the license manager on a different computer, then your license file can only contain two lines: the `SERVER` line and the `USE_SERVER` line.

THE VENDOR LINE

The `VENDOR` line defines the name of the LMCOMSOL vendor daemon. This name cannot be changed. The vendor daemon is a process that has to be running together with the license manager and is automatically started when the license manager is started. The LMCOMSOL vendor daemon requires its own port number. In the example above, the default port number `1719` is shown.

If the license manager is running on a computer with an active firewall and the COMSOL client is outside of that firewall, at least two port numbers must be opened up in the license server's firewall to allow client computers to connect to the license manager and the vendor daemon.

Using the example license file above, configure the firewall to allow access to the port numbers `1718` and `1719`. If you have chosen other port numbers and modified the `license.dat` file accordingly, configure the firewall to allow access

to your chosen port numbers. If you are unsure about which port numbers are free or how to enable firewall port access, contact your system administrator.

You cannot modify anything in the `license.dat` file except the license server name and (if necessary) port numbers, or the license might not work.

THE SERIAL LINE

The SERIAL line contains information on the license type, license number, and the products included in the license.

THE INCREMENT AND FEATURE LINES

The INCREMENT or FEATURE lines contain a product name, version, expiration date, and the number of available licenses. The example file above shows that the user has a perpetual (permanent) COMSOL 4.4 Floating Network License allowing four concurrent users of COMSOL Multiphysics and two concurrent users of the Heat Transfer Module. The number after “SIGN=” at the end of each INCREMENT line contains a license key. Long lines can be broken by a continuation character (\).

The Feature Names

The following table contains the FEATURE names for all products in the COMSOL 4.4 product suite:


PRODUCT/FEATURE	FEATURE NAME
COMSOL Multiphysics	COMSOL
COMSOL Multiphysics GUI	COMSOLGUI
COMSOL Multiphysics Floating Network License	CLIENTSERVER, CLUSTERNODE
AC/DC Module	ACDC
Acoustics Module	ACOUSTICS
Batteries & Fuel Cells Module	BATTERIESANDFUELCELLS
CAD Import Module	CADIMPORT, CADREADER
CFD Module	CFD
Chemical Reaction Engineering Module	CHEM
Corrosion Module	CORROSION
ECAD Import Module	ECADIMPORT
Electrochemistry Module	ELECTROCHEMISTRY
Electrodeposition Module	ELECTRODEPOSITION
Fatigue Module	FATIGUE

PRODUCT/FEATURE	FEATURE NAME
File Import for CATIA V5	CATIA5
Geomechanics Module	GEOMECHANICS
Heat Transfer Module	HEATTRANSFER
LiveLink™ for AutoCAD®	LLAUTOCAD
LiveLink™ for Creo™ Parametric	LLCREOPARAMETRIC
LiveLink™ for Excel®	LLEXCEL
LiveLink™ for Inventor®	LLINVENTOR
LiveLink™ for MATLAB®	LLMATLAB
LiveLink™ for Pro/ENGINEER®	LLPROENGINEER
LiveLink™ for Solid Edge®	LLSOLIDEDGE
LiveLink™ for SolidWorks®	LLSOLIDWORKS
LiveLink™ for SpaceClaim®	LLSPACECLAIM
MEMS Module	MEMS
Mixer Module	MIXER
Molecular Flow Module	MOLECULARFLOW
Multibody Dynamics Module	MULTIBODYDYNAMICS
Nonlinear Structural Materials Module	NONLINEARSTRUCTMATERIALS
Optimization Module	OPTIMIZATION
Particle Tracing Module	PARTICLETRACING
Pipe Flow Module	PIPEFLOW
Plasma Module	PLASMA
RF Module	RF
Semiconductor Module	SEMICONDUCTOR
Structural Mechanics Module	STRUCTURALMECHANICS
Subsurface Flow Module	SUBSURFACEFLOW
Wave Optics Module	WAVEOPTICS

Installing the License Manager

The FlexNet license manager is automatically installed when installing COMSOL unless otherwise specified on the Features page of the COMSOL Installer; see

“Features Page” on page 19. The check box for the license manager components can be found last in the list of software components, as seen in the picture below:



If you do not intend to run the license manager software on the computer for which you are installing COMSOL, you can clear this check box during installation. The license manager components require a moderate amount of hard disk space (about 26MB).

If you want to install COMSOL on the same computer as the license manager, first perform a complete COMSOL installation including the license manager software components. When finished, skip the remainder of this section and continue with “Starting the License Manager” on page 40.

To install only the license manager, follow the installation instructions for COMSOL earlier in this document and on the Features page and clear all check boxes except the one for the license manager.

AUTOMATED LICENSE MANAGER INSTALLATION

Alternatively, the license manager can be installed using an automated installation process with minimal user interaction; see “Automated Installation” on page 25. Set `licmanager = 1` in the answer file to install the license manager.


Starting the License Manager

The license manager can be started manually, or it can be configured to run automatically as a service each time the license server is restarted.

STARTING THE MANAGER AUTOMATICALLY AS A SERVICE

To set up the license manager as a service from the FlexNet Control Panel (LMTOOLS):

- 1 Locate the `COMSOL44\license\win32` (Windows 32-bit) or `COMSOL44\license\win64` (Windows 64-bit) folder and run `lmtools.exe`. Alternatively, run LMTOOLS from the Windows Start menu, available under `COMSOL 4.4>License Tools>LMTOOLS`.
- 2 On the Service/License File page choose **Configuration using Services**.
- 3 Click the **Configure Services** tab.



- 4 Make an entry in the **Service Name** field, for example, COMSOL License Manager.
- 5 Specify the full paths to `lmgrd.exe` and `license.dat` by browsing to their locations on your hard drive. The default location for `lmgrd.exe` is `C:\Program Files\COMSOL\COMSOL44\license\win64\lmgrd.exe`, and for the license file, it is `C:\Program Files\COMSOL\COMSOL44\license\license.dat`. For the debug log file, you can use any name of your choice, for example, `comsol44.log`. For convenience you can place this next to your license file at: `C:\Program Files\COMSOL\COMSOL44\license\comsol44.log`.



Make sure your Windows user account has read/write permission for the folder of the debug log file, otherwise the debug log file is not created.

Select the **Use Services** check box (this might not be possible on all platforms, but it is recommended when available) and then the **Start Server at Power Up** check box.

- 7 Click **Save Service**. The license manager now starts automatically when you reboot the license server computer. If you want to start the license manager right away without restarting the license server computer, click **Start Server** on the **Start/Stop/Reread** page of the FlexNet Control Panel.

STARTING THE LICENSE MANAGER MANUALLY

To start the license manager manually, browse to the `license\win32` (Windows 32-bit) or `license\win64` (Windows 64-bit) folder. Now, in a Windows command window enter

```
lmgrd -c ..\license.dat -l ..\comsol44.log
```

The license manager is now ready to distribute licenses over the network. It writes debug information to the log file `COMSOL44\license\comsol44.log`.

Verifying that the License Manager is Running

Once you start the license manager, it is good practice to verify that the license manager service is running. Start the Windows Task Manager and go to the Services page. Check that the COMSOL License Manager service is running.

Starting COMSOL

After the installation is complete and the license manager daemons are running on the license server, you can start using COMSOL. For more information on how to run COMSOL, see [“Running COMSOL on Windows”](#) on page 43.

Changing the License

If you have received a new license file—for example, when adding COMSOL products to an existing license—replace the current license file with the new one. Double-check the contents of this file to make sure it lists the products that the license includes. See also [“The Feature Names” on page 37](#).



When the license file has changed, you must restart the license manager; otherwise, it continues to use the old license file still in memory.

RESTARTING THE LICENSE MANAGER

To restart the license manager, follow these steps:

- 1 In the Windows Start menu, choose **COMSOL4.4>License Tools>LMTTOOLS**.
- 2 In the FlexNet Control Panel, click, in this order, **Stop Server**, **Reread License File**, and **Start Server**.

OBTAINING A HOSTID

If you need to verify the hostid of the license server, you can follow the steps for [“Obtaining the Hostid” on page 8](#). Alternatively, if COMSOL is already installed on the license server, you can determine the hostid by running the `lmhostid` command

```
COMSOL44/license/win32/lmutil lmhostid
```

or

```
COMSOL44/license/win64/lmutil lmhostid
```

for Windows 32-bit and Windows 64-bit, respectively.

The hostid is typically the Ethernet address (also called a MAC address) of the network card of your computer. An Ethernet address has six bytes, each with two hexadecimal digits. Thus, the full hostid has twelve hexadecimal digits.

Alternatively, the hostid can be the volume serial number of your C hard drive. The volume serial number has 4 bytes, each with two hexadecimal digits. In this case, the full hostid has eight hexadecimal digits.

Troubleshooting License Errors

If you have questions or problems with your installation, see [“Troubleshooting License Errors” on page 91](#).

Running COMSOL on Windows

After the installation is finished there is a COMSOL Multiphysics 4.4 shortcut icon on the Windows desktop:



as well as a COMSOL 4.4 folder on the Windows Start menu. To start COMSOL, double-click the desktop icon or select COMSOL Multiphysics 4.4 from the Windows Start menu. For Windows 8 instructions, see “[Running COMSOL on Windows® 8](#)” on page 44.

CROSS-PLATFORM USER INTERFACE

The default user interface for COMSOL is a Windows application. There is also a cross-platform user interface that you can start by going to the `bin\win32` (32 bit) or `bin\win64` (64 bit) folder in the COMSOL installation directory and double-clicking `comsolxp1.exe`. The cross-platform user interface is identical to the interface on Linux and the Mac.

The COMSOL Folder on The Windows Start Menu

Depending on which COMSOL products and software components you have licensed and installed, the COMSOL 4.4 folder on the Start menu contains a selection of the items in the following list:

- COMSOL Multiphysics 4.4: Starts the COMSOL Desktop.
- Model Animations: Launches a web browser with a selection of model animations at: www.comsol.com/showroom/animations
- Uninstall COMSOL Multiphysics 4.4: Starts the COMSOL Uninstaller. For more information, see “[Removing \(Uninstalling\) the COMSOL Installation](#)” on page 23.
- 32-bit: Contains COMSOL 32-bit executables

- Client Server
 - COMSOL Multiphysics 4.4 Client: Starts a COMSOL Client that can be connected to a COMSOL Server.
 - COMSOL Multiphysics 4.4 Server: Starts a COMSOL Server that a COMSOL Client can connect to.


For more information on running COMSOL in client-server mode, see [“Running COMSOL in Client-Server Mode” on page 47](#).

- COMSOL with MATLAB: This is available if you have licensed the LiveLink *for* MATLAB[®]. It starts MATLAB and sets up all necessary paths. It also starts a COMSOL Server connected to MATLAB. See also [“Running COMSOL with MATLAB” on page 52](#).
- Documentation: Opens a folder that contains COMSOL documentation shortcuts.
- License Tools: Starts the FlexNet license manager control panel (LMTOOLS). For more information, see [“License Manager Installation on Windows” on page 33](#).


Running COMSOL on Windows[®] 8

On Windows 8, COMSOL can be started from three different locations:


- There is a COMSOL Multiphysics tile on the Windows Start Screen:



- There are two icons on the Window Desktop for COMSOL Multiphysics and COMSOL Help Desk:




- The Windows All apps page has three tiles for COMSOL Help Desk, COMSOL Launchers, and COMSOL Multiphysics:



Starting COMSOL for a Classkit License

If you have a Classkit License, you start it by double clicking its dedicated Windows desktop icon:



For Windows 8, corresponding tiles and desktop icons are added.

Creating Desktop Shortcuts Manually

Sometimes it is necessary to create the COMSOL shortcuts manually, for example, when COMSOL is installed on a shared network drive.

1 Locate the COMSOL executable. Its default location is

```
C:\Program Files\COMSOL\COMSOL44\bin\win64\comsol.exe
```

or

```
C:\Program Files\COMSOL\COMSOL44\bin\win32\comsol.exe
```

for Windows 64-bit and Windows 32-bit, respectively

2 Right-click `comsol.exe` and select **Create shortcut**, which creates a shortcut with a default name **comsol.exe - Shortcut**. If this shortcut is not created on the Desktop, then move it there by drag-and-drop.

CREATING A DESKTOP SHORTCUT MANUALLY FOR THE CROSS-PLATFORM USER INTERFACE

The cross-platform user interface for COMSOL that is available on Mac and Linux has a slightly different look-and-feel than the user interface for Windows. You can get access to the cross-platform user interface from

```
C:\Program Files\COMSOL\COMSOL44\bin\win64\comsolxpl.exe
```

assuming that you are running the 64-bit version and that the default installation location has not changed by you during installation.

To create a shortcut to the cross-platform user interface, right-click `comsolxpl.exe` and select **Create shortcut**, which creates a shortcut with a default name **comsolxpl.exe - Shortcut**. If this shortcut is not created on the Desktop, then move it there by drag-and-drop.

CREATING DESKTOP SHORTCUTS MANUALLY FOR A CLASSKIT LICENSE

If you manually create a desktop shortcut for a Classkit License, then, in addition to the steps above, the shortcut's Target needs to be modified with additional options. Right-click the **COMSOL** shortcut icon and select **Properties**. Change the text string in the **Target** field to

```
"C:\Program Files\COMSOL\COMSOL44\bin\win64\comsol.exe" -Dcs.ckl
```

```
"C:\Program Files\COMSOL\COMSOL44\bin\win64\comsolclasskit.ini"
```

(The complete text string must be written on a single row.)

or

```
"C:\Program Files\COMSOL\COMSOL44\bin\win32\comsol.exe" -Dcs.ckl
```

```
"C:\Program Files\COMSOL\COMSOL44\bin\win32\comsolclasskit.ini"
```

for Windows 64-bit and Windows 32-bit, respectively.

Here, `C:\Program Files\COMSOL\COMSOL44` represents the default COMSOL installation directory and this can be changed in the Target field text string if your installation is placed in a different folder.

Running COMSOL in Client-Server Mode

When you start COMSOL by, for example, double-clicking the Windows desktop icon, COMSOL is run as a single application that includes both the COMSOL Client and COMSOL Server, as explained later in this section. However, the COMSOL Client/Server architecture lets you access the COMSOL Server—the COMSOL computational engine—as a separate process. For example, the COMSOL Desktop can act as a COMSOL Client when connected to a COMSOL Server.



The license server is not the same as a COMSOL Server. The license manager can run on a computer different from both the ones used by COMSOL Desktop and COMSOL Server.


You need a Floating Network License to run the COMSOL Server and the COMSOL Client on separate computers. However, any COMSOL license is sufficient for running the Client and the Server on the same computer.

The Client and Server need not run on the same platform. For example, you can run the COMSOL Desktop on Windows connecting to a COMSOL Server on a Linux or Mac computer. This enables offloading heavy-duty computations from your personal laptop or desktop to run just the COMSOL Desktop graphical user interface. A typical use would be to run the COMSOL Server on a computer with large amounts of memory (RAM) and processing power and to use your personal computer for pre- and postprocessing with the COMSOL Desktop.

STARTING A COMSOL SERVER

The COMSOL server is a single user server allowing multiple sessions by the same user, one session at a time. To start the COMSOL Server, click COMSOL Multiphysics Server in the Client Server folder underneath your COMSOL folder on the Windows Start menu. (On Windows 8 you find this on the All apps page under COMSOL Launchers.) When you start the COMSOL Server from the Windows Start menu, a command window appears asking you for a username and


password. You can use any username and password of your choice, it is only used for connecting a COMSOL Client with a COMSOL Server.



When the COMSOL Server starts, it listens for a COMSOL Client connection on the port listed in the command window. In the example above it is port 2036.


CONNECTING A COMSOL CLIENT TO A COMSOL SERVER

You can start a COMSOL Client session by clicking COMSOL Multiphysics Client in the Client Server folder underneath your COMSOL folder on the Windows Start menu. (On Windows 8 you find this on the All apps page under COMSOL Launchers.) You can also connect to a COMSOL server from the COMSOL Desktop by selecting Connect to Server from the File menu. When you start the Client, a Connect to Server window appears prompting you for a computer name (Server) where the COMSOL Server is running, Port number, Username, and Password.



Once you have filled out this information and clicked OK, the COMSOL Server command window indicates that a COMSOL Client has connected. For more information on running COMSOL in Client/Server mode, see the *COMSOL Multiphysics Reference Manual*.

Running COMSOL in Batch Mode

You can submit COMSOL batch jobs from the COMSOL Desktop and the command line. To run a COMSOL batch job, you need to make the Batch feature visible: in the Model Builder tree, click the Show button () and select Advanced Study Options. In the Model Builder, right-click a Study node and select Batch to create batch jobs. From the Windows command window, you can start batch jobs using the `comsolbatch` command. This is an example of how such a command could look like:

```
comsolbatch -inputfile in.mph -outputfile out.mph
```

To run a specific study add the command line option `-study <tag>`, where `<tag>` is the tag of the study to run, for instance, `std1`. To see the tag, select **Model Builder Node Label>Show Name and Tag** in the COMSOL Desktop (on the Home toolbar in Windows, or from the **Windows** menu in Linux and Mac).

The *COMSOL Multiphysics Reference Manual* has a dedicated section on running COMSOL from the Windows command window, including a list of COMSOL commands and associated syntax.

Running COMSOL on Multicore Computers

COMSOL supports two modes of parallel operation: shared-memory parallel operations and distributed-memory parallel operations, including cluster support. This section covers shared-memory processing, or multithreading, which is important for the performance of COMSOL computations. Some terms that are frequently used when describing multithreading are:

- *Core*: The core is a processor core used in shared-memory parallelism by a computational node with multiple processors.
- *Speedup* is how many times faster a job runs on N cores compared to 1 core, on a specific compute node. The speedup depends on the simulation type, the hardware used, and hardware drivers used.

In Windows, the default number of processor cores used by COMSOL is the total number of available physical cores. For example, if you have a 2 x dual core machine, 4 cores are used in parallel by a COMSOL process.

Here is how to find out how many processor cores your Windows machine has (applicable for computers that do not have Intel[®] Hyper-Threading Technology and AMD[®] computers that are not based on Bulldozer):


- 1 In the Windows file browser, right-click **Computer** or **My Computer**, select **Properties**.
- 2 Click **Advanced system settings**. Go to the **Advanced** tab.
- 3 Click the **Environment Variables** button and look in the System variables list. Look for `NUMBER_OF_PROCESSORS` and check its value. This is actually the number of cores. If you have two processors with 2 cores each, this number is 4. Alternatively, start a Windows command window and type

```
echo %NUMBER_OF_PROCESSORS%
```

If you want COMSOL to leave out one or more processor cores you can set the number of cores used for a computational job in the Preferences dialog box under Memory and processors (by first selecting the Number of processors check box and then entering the number of processor cores to use).

You can also change the default behavior of COMSOL by setting the environment variable `COMSOL_NUM_THREADS` to the desired number of cores. See the *COMSOL Multiphysics Reference Manual* for more information.

Running COMSOL on Clusters

You can launch COMSOL cluster jobs from the COMSOL Desktop and the command line. To run COMSOL on a cluster, you need to make the cluster features visible: in the Model Builder tree, click the Show button () and select Advanced Study Options. Then in the Model Builder, right-click a Study node and select Cluster Computing or Cluster Sweep to create cluster jobs. Cluster computing requires a Floating Network License.

The following terms occur frequently when describing the hardware for cluster computing and shared-memory parallel computing:

- **Compute node:** The compute nodes are where the distributed computing occurs. Each distributed COMSOL process resides in a compute node and communicates with other compute nodes using MPI (message-passing interface).
- **Host:** The host is a physical machine (hardware) with a network adapter and unique network address. The host is part of the cluster. It is sometimes referred to as a physical node.
- **Core:** The core is a processor core used in shared-memory parallelism by a computational node with multiple processors.

The number of used hosts and the number of computational nodes are usually the same. For some special problem types, like very small problems with many parameters, it might be beneficial to use more than one computational node on one host.

A tutorial model for cluster testing is included in the Model Libraries window under COMSOL Multiphysics>Tutorial models>micromixer_cluster

QUICK TROUBLESHOOTING

- Your first step is to make sure you have the latest release installed. Check that you have COMSOL 4.4 or later. Also make sure to install the latest product updates.
- For Windows HPCS, log in to each node with remote desktop and start the COMSOL Desktop GUI. No error messages should be displayed.
- If you get the error message “Process status indicates that process is running,” then cancel any running jobs in the Windows HPCS Job manager or other scheduler that you use. In the COMSOL Desktop, locate the External Process page at the bottom right. Click the Clear Status button.

For more information about how to run COMSOL in parallel on Windows clusters, see the *COMSOL Multiphysics Reference Manual*. For installation on Clusters, see “[Cluster Installation](#)” on page 32.

Running COMSOL on the Cloud

COMSOL supports cloud computing using Linux through Amazon Elastic Compute Cloud™ (Amazon EC2)™. See the PDF version of *Running COMSOL on the Amazon™ Cloud* for further information: www.comsol.com/ec2_manual.

Running COMSOL with MATLAB

Running COMSOL with MATLAB requires a LiveLink™ *for* MATLAB® license. To run COMSOL with MATLAB, double-click the COMSOL Multiphysics 4.4 with MATLAB icon on the desktop.



Alternatively, start COMSOL with MATLAB from the Start menu by pointing to Programs, then to COMSOL 4.4, and then select COMSOL Multiphysics 4.4 with MATLAB. For Windows 8, corresponding tiles and desktop icons are added, and you can click COMSOL Multiphysics 4.4 with MATLAB on the start screen to launch COMSOL.

Running COMSOL with MATLAB starts a COMSOL Server and a MATLAB Desktop. The COMSOL Desktop is not involved. You can change the path to the MATLAB installation in the Preferences window accessed from the Options menu of the COMSOL Desktop. For more information, see the LiveLink™ *for* MATLAB® documentation.

STARTING COMSOL WITH MATLAB USING THE GRAPHICS SERVER

To display the plot in a COMSOL graphics window you need to run COMSOL with MATLAB using the graphics server. To do so, append the flag `-graphics` to the COMSOL with MATLAB target path.

Installation Over the Internet

INSTALLATION OF A TRIAL LICENSE OVER THE INTERNET

A trial license can be given to you with the intention to test the software without any payment obligation for noncommercial and nonproduction use. This option is not available in all regions.

Installation of a Single User Trial License on Mac requires a license passcode. A passcode has a form similar to:

FFFFFFFF - TYUS - 123456 - 1234567 - 123456789

This is usually sent to you by your COMSOL representative by email. Once you locate your passcode, follow these steps to prepare for download and installation:

- 1 Click the link for downloading the software as given in the software download email from your COMSOL representative. This link is identical or similar to: www.comsol.com/support/download/trial.
- 2 If you haven't already created a COMSOL Access account, you will be prompted to create it. While creating the account, enter your trial passcode to associate it with your account information.

If you already have created a COMSOL Access account, then the link www.comsol.com/support/download/trial directs you to a page where you can enter the passcode:

- 3 Follow the web-based instructions to download the software.
- 4 Continue with the instructions in the section “[Downloading the COMSOL Installer](#)” on page 56.


INSTALLATION OF A PAID-FOR LICENSE OVER THE INTERNET

Installation of any paid-for license on Mac requires a license file that is sent to you by your COMSOL representative by email. To be able to generate the license file, information about your hardware is needed in the form of a hostid (host ID). The hostid is used to lock the license to your hardware and needs to be sent by you to a COMSOL representative prior to the license file being generated.

Obtaining the Hostid

Follow these steps to obtain a hostid:

- 1 Launch the application **Network Utility** found in the **Applications/Utilities** folder.
- 2 Click the **Info** tab to the left.
- 3 Select **Network Interface (en0)**. This corresponds to your Ethernet card.
- 4 The hostid is the Hardware Address—as shown in the figure below, but with the colons (:) removed. If you plan to install on a computer with a wireless network card, report the hardware address for both Network Interface (en0) and Network Interface (en1).



Obtaining the Host Name

If you have been informed by your COMSOL representative that you need to run the FlexNet license manager for your installation, then you also need the Host Name. To get the Host Name, launch the **Terminal** application; then enter `hostname` at the terminal prompt.

If your network administrator prefers to use a fixed IP address for this particular computer, this IP Address could be optionally used in place of the Host Name. For more information on license manager installation, see [“License Manager Installation on Mac OS X” on page 61](#).

Obtaining the License File from a COMSOL Representative

Send the hostid information, as well as Host Name, if applicable, in an email to your COMSOL representative, who will respond with an email with an attached license file (`license.dat`). Save this file to any location on your computer. You need to refer to it during installation. The license file is a text file. Below is an example of the contents of a `license.dat` file for a Single User License on Mac. This example license file shows that the licensed products are

COMSOL Multiphysics, Particle Tracing Module, Subsurface Flow Module, and LiveLink™ for Excel®.

```
#-----  
# COMSOL 4.4 NSL License No: 1234567 Windows/Mac  
# Visit www.comsol.com/install for latest installation instructions  
#-----  
FEATURE SERIAL LMCOSOL 4.32 permanent uncouted \  
    VENDOR_STRING=C,18000100200 HOSTID=ANY sort=100 SN=1234567 \  
    TS_OK SIGN=8045890A6FE4  
FEATURE COMSOL LMCOSOL 4.32 permanent uncouted HOSTID="70f2b13f4dfd \  
    0116b8cc761a" PLATFORMS="i86_n x64_n i86_mac x64_mac" \  
    SN=2076312 SIGN=E607EB680852  
FEATURE PARTICLETRACING LMCOSOL 4.32 permanent uncouted \  
    HOSTID="70f1a12f4dfc 0026b9cc760a" PLATFORMS="i86_n x64_n \  
    i86_mac x64_mac" SN=2076312 SIGN=3835733C6290  
FEATURE SUBSURFACEFLOW LMCOSOL 4.32 permanent uncouted \  
    HOSTID="70f1a12f4dfc 0026b9cc760a" PLATFORMS="i86_n x64_n \  
    i86_mac x64_mac" SN=2076312 SIGN=3A9BA162C9E4  
FEATURE LLEXCEL LMCOSOL 4.32 permanent uncouted HOSTID="70f1a12f4dfc \  
    0026b9cc760a" PLATFORMS="i86_n x64_n i86_mac x64_mac" \  
    SN=2076312 SIGN=EE9C11E44356  
FEATURE COMSOLGUI LMCOSOL 4.32 permanent uncouted \  
    HOSTID="70f1a12f4dfc 0026b9cc760a" PLATFORMS="i86_n x64_n \  
    i86_mac x64_mac" SN=2076312 SIGN=0D0A83382550
```


A Single User License file can normally not be edited or changed in any way by the user but has to be identical to the one sent to you by a COMSOL representative. However, if you were sent a license file that requires a license manager, then minor edits are required. For information on the type of license file required for installations using a license manager, see “[The License File](#)” on page 62.

Registering with COMSOL Access

Once you have saved your license file, follow these steps to register or login to COMSOL Access and to start the installation:

- 1 Click the link for downloading the software as given in the software download email from your COMSOL representative. This link is identical or similar to: www.comsol.com/product-download.
- 2 If you haven't already created a COMSOL Access account, you will be prompted to create it. While creating the account, point to your license file (`license.dat`) to associate it with your account information.
If you already created a COMSOL Access account, then you can associate the license file on the COMSOL Access page with your account under Manage Licenses at www.comsol.com/access/licenses/
- 3 Continue with the instructions in the next section.

DOWNLOADING THE COMSOL INSTALLER

- 1 Go to the web page www.comsol.com/product-download.
 - 2 You are now given the option of installing COMSOL using the **Online Installer**. (For the DVD option see “[Installation from Downloaded DVD Image](#)” on page 11.) In addition, there are two further options of Compact Installation or Full Installation:
 - **Compact Installation:** Includes the on-line documentation. The model library tutorials are stripped of solutions, which reduces download time. The size of this download ranges from 600 MB to 1.6 GB depending on your license.
 - **Full Installation:** Includes the full documentation and the complete model library with meshes and solutions for your licensed products. The size of this download ranges from 1.0 GB to 3.7 GB depending on your license.
-  If you have problems downloading (such as **Error downloading file. Connection refused: connect**), please review this knowledge base entry: www.comsol.com/support/knowledgebase/1149. If you still have problems, please contact your local COMSOL representative or technical support from the Support Center page at www.comsol.com/support.

Selection one of the options for Compact Installation or Full Installation.


Clicking one of the install buttons starts the download of the COMSOL Installer. For Mac, the file to download is called `COMSOL44_mac.dmg` for the Full Installation and `COMSOL44_compact_mac.dmg` for the Compact Installation.

STARTING THE INSTALLER FOR INSTALLATION OVER THE INTERNET

The COMSOL Installer is a user interface tool that guides you through the installation process. Start the COMSOL Installer by first mounting the downloaded file by double-clicking it. Then run the COMSOL Installer application `COMSOL Installer`. The COMSOL 4.4 Installer window should now appear. Now continue with the instructions in the section “[Running The COMSOL Installer](#)” on page 58.

Installation from Downloaded DVD Image

Installation from a DVD where the DVD image is downloaded from COMSOL for off-line installation requires you to first create a COMSOL Access account as described in the section “[Installation Over the Internet](#)” on page 7.

- 1 Once you are logged in to COMSOL Access, you are now given the option of installing COMSOL using the **Online Installer** or to download the **DVD Image for Offline Installation**. This section covers the DVD Image option. In addition, there are two further options of Compact Installation or Full Installation:
 - **Compact Installation:** Includes the on-line documentation. The model library tutorials are stripped of solutions, which reduces download time. The size of this download ranges from 600 MB to 1.6 GB depending on your license.
 - **Full Installation:** Includes the full documentation and the complete model library with meshes and solutions for your licensed products. The size of this download ranges from 1.0 GB to 3.7 GB depending on your license.
-  If you have problems downloading (such as **Error downloading file. Connection refused: connect**), please review this knowledge base entry: www.comsol.com/support/knowledgebase/1149. If you still have problems, please contact your local COMSOL representative or technical support from the Support Center page at www.comsol.com/support.
- 2 In the section for the DVD Image option, click one of the buttons for **Compact DVD Download** or **Full DVD Download**. Clicking one of the install buttons starts the download of the COMSOL DVD Image. The file to download is called `COMSOL44_dvd.iso`.
- 3 When you have downloaded the DVD image, you can install directly from the downloaded DVD image by double-clicking it to mount it. Alternatively, burn the DVD image to a disc to install. If you want to burn the DVD image to a disc:
 - a Launch the **Disk Utility** application from **Applications/Utilities**.
 - b Click the **Burn** toolbar button. Select the DVD image in the file dialog box and open it.
 - c Insert an empty DVD in the DVD drive and click **Burn** in the dialog box in **Disk Utility**.

Starting the Installer from DVD or DVD Image

This section applies if you have received a DVD from a COMSOL representative or if you have burned a DVD image downloaded from COMSOL for off-line installation.

The COMSOL Installer is a user interface tool that guides you through the installation process. To start the installer:

- 1 Insert the COMSOL DVD into the DVD drive (or mount the image).
- 2 Launch the COMSOL Installer application from the Finder.
- 3 The COMSOL 4.4 Installer window appears. Now continue with the instructions in the section [Running The COMSOL Installer](#) below.

Installation from USB Flash Drive

This section applies if you have received a USB Flash Drive from a COMSOL representative.


STARTING THE INSTALLER FROM A USB FLASH DRIVE

The COMSOL Installer is a user interface tool that guides you through the installation process. To start the installer:

- 1 Connect the USB Flash Drive to your computer.
- 2 Launch the COMSOL Installer application from the Finder.
- 3 The COMSOL 4.4 Installer window appears. Now continue with the instructions in the section [Running The COMSOL Installer](#) below.

Running The COMSOL Installer

The steps for running the COMSOL Installer are independent of the installation media option you used. If you have followed the above instructions, the COMSOL Installer should now appear. Now continue with the instructions for Windows in the section “[Running the COMSOL Installer](#)” on page 13. The procedure is the same for Mac OS X with the following exceptions:

-  COMSOL does not work if the path to the COMSOL folder, or the name of the COMSOL folder itself, contain spaces.

You cannot browse to the MATLAB installation directory directly. You need to enter it manually. MATLAB is installed in the /Applications directory, for example, as /Applications/MATLAB_R2013b.app.

Automated Installation

You can install COMSOL using an automated installation process with minimal user interaction. This method requires installation from DVD or DVD image. The documentation on how to create an answer file is available in the template, `setupconfig.ini`, which is available on the DVD. When an answer file is created, start the installation by running

```
<path to DVD>/setup -s <answer file path>
```

where `<answer file path>` is the path to the answer file.

Removing (Uninstalling) the COMSOL Installation

The COMSOL 4.4 installation adds files only in the COMSOL44 folder. To remove the COMSOL installation, delete the COMSOL44 folder including all subfolders.

Product Updates and Model Library Update

COMSOL periodically releases product updates with improvements and corrections to reported problems. By default, COMSOL checks for updates at startup. You can turn this feature on and off from the COMSOL Desktop Preferences Window. Here you can also configure settings for the Model Library Update.

The COMSOL Model Library is updated on a regular basis by COMSOL. To open the Model Library Update window from the File>Help menu (Windows users) or from the Help menu (Mac and Linux users), select Update COMSOL Model Library.

This connects you to the COMSOL Model Update website where you can access the latest models and model updates. This includes models that have been added or improved since the latest product release.

Using the Updates section in the Preferences dialog box, which you open from the COMSOL Desktop, you can configure proxy server settings as well as model and documentation directories for the Model Library Update. See the *COMSOL*

Multiphysics Reference Manual for more information including command-line options for the Model Libraries.

Changing the Path to the MATLAB® Installation

You can change the path to the MATLAB installation in the **Preferences** window accessed from the **Options** menu of the COMSOL Desktop. For more information, see the LiveLink™ *for* MATLAB® documentation.

License Manager Installation on Mac OS X

Many of the instructions for installing the FlexNet license manager are similar to those for Windows. This section covers only the differences when installing on Mac OS X. For general information on the license manager software, see “[License Manager Installation on Windows](#)” on page 33.


FlexNet License Manager Software Components

The license manager consists of the following software components:

- License manager daemon (`lmgrd`)
- Vendor daemon (`LMCOMSOL`)
- FlexNet utility program (`lmutil` and others)

The two daemons (`lmgrd` and `LMCOMSOL`) run on the license server. When a user starts COMSOL on a client computer, communication is established through the network from the client to the license server and the license manager daemon (`lmgrd`). That daemon in turn makes a request to the vendor daemon (`LMCOMSOL`), which releases licenses according to information in the `license.dat` file. The FlexNet utility programs are used to handle license server management tasks.

FlexNet License Manager Documentation

For detailed information on the FlexNet license manager software, click the  button and choose Help>Documentation (Windows) or select Help>Documentation (Mac and Linux) and scroll to the bottom of the page to locate a PDF copy of the *FlexNet License Administration Guide*.

The License File

The license file for use on Mac OS X is identical to that of Windows. See [“The License File” on page 35](#) for more information.

Installing the License Manager

The FlexNet license manager is automatically installed when installing COMSOL unless otherwise specified on the Features page of the COMSOL Installer; see [“Features Page” on page 19](#). The check box for the license manager components can be found last in the list of software components.

If you want to install COMSOL on the same computer as the license manager, first perform a complete COMSOL installation including the license manager software components. When finished, skip the remainder of this section and continue with [“Starting the License Manager” on page 62](#).

To install only the license manager, follow the installation instructions for COMSOL earlier in this document and, on the Features page, clear all check boxes except the one for the license manager.

AUTOMATED LICENSE MANAGER INSTALLATION

Alternatively, the license manager can be installed using an automated installation process with minimal user interaction; for this option, see [“Automated Installation” on page 59](#). Set `licmanager = 1` in the answer file to install the license manager.

Starting the License Manager

Either start the license manager manually or let it run automatically at startup.

STARTING THE LICENSE MANAGER MANUALLY

To start the license manager manually:

- 1 Launch the Terminal application.
- 2 Change directory to the `license/maci64` directory:

```
cd /Applications/COMSOL44/license/maci64
```

3 Then enter

```
./lmgrd -c ../license.dat -l /var/tmp/comsol44.log
```

The server is now ready to distribute licenses over the network. It writes any debug information to the log file `/var/tmp/comsol44.log`.

STARTING THE LICENSE MANAGER AUTOMATICALLY AT STARTUP

A folder `COMSOL_Lmgr` located in the folder `COMSOL44/license/maci64` contains a script that can automatically start the license manager when you start the computer. By installing and configuring this folder, the license manager does not need to be started manually.

- 1 Go to the top level `/Library` folder on your startup disk.
- 2 In the `Library` folder, create a folder `StartupItems` if it does not already exist.
- 3 Move or copy the folder `COMSOL_Lmgr` to the `StartupItems` folder.
- 4 Open the file `COMSOL_Lmgr` in a text editor, for example, `TextEdit`.
- 5 Edit the line

```
FP=<COMSOLPATH>
```

by replacing `<COMSOLPATH>` with the path to the `COMSOL` folder. If `COMSOL` is installed in the `Applications` folder this path is

```
FP=/Applications/COMSOL44
```

- 6 Edit the line

```
USERNAME=<username>
```

by replacing `<username>` with your username.



To run the `COMSOL_Lmgr` file it must have the correct file permission that include executable permission for the root user. To make sure that it has the correct permission, enter the following commands:

```
sudo chown -R root:wheel /Library/StartupItems/COMSOL_Lmgr
sudo chmod -R 0755 /Library/StartupItems/COMSOL_Lmgr
```

Restart the computer to test the license manager installation. During startup a message `Starting COMSOL License Manager` should appear.

Verifying that the License Manager is Running

Once you start the license manager, it is good practice to verify that the license manager processes are running. Start the Activity Monitor and check for the vendor daemon (LMCOMSOL) and the license manager (lmgrd) in the list of processes.

Starting COMSOL

After the installation is complete and the license manager daemons are running on the license server, you can start using COMSOL. For more information on how to run COMSOL, see [“Running COMSOL on Mac OS X” on page 66](#).

Changing the License

If you have received a new license file—for example, when adding COMSOL products to an existing license—replace the current license file with the new one. Double-check the contents of this file to make sure it lists the products that the license includes.



When the license file has changed, you must restart the license manager; otherwise, it continues to use the old license file still in memory.

RESTARTING THE LICENSE MANAGER

To restart the license manager:

- 1 Launch the Terminal application.
- 2 Change the directory to the `license/maci64` (64-bit)

```
cd /Applications/COMSOL44/license/maci64
```

- 3 Enter the commands

```
./lmdown -c ../license.dat  
./lmgrd -c ../license.dat -l /var/tmp/comsol44.log
```


OBTAINING A HOSTID

If you need to verify the hostid of the license server, you can follow the steps in [“Obtaining the Hostid” on page 54](#). Alternatively, if COMSOL is already installed on the license server, you can determine the hostid by executing the `lmhostid` command

```
COMSOL44/license/maci64/lmhostid
```

The hostid is typically the Ethernet address (also called a MAC address) of the network card of your computer. An Ethernet address has six bytes, each with two hexadecimal digits. Thus, the full hostid has twelve hexadecimal digits.

Troubleshooting License Errors

If you have questions or problems with your installation, see [“Troubleshooting License Errors” on page 91](#).

Running COMSOL on Mac OS X

The COMSOL Applications

After the installation is finished there are several COMSOL applications available. How many are available depends which products and licenses you have:

COMSOL Multiphysics This is the primary application for running COMSOL Multiphysics. It launches COMSOL Multiphysics as a standalone application.

COMSOL Multiphysics (Classkit License) This application launches COMSOL Multiphysics for a Classkit License. This application is only available if you have a Classkit License.

COMSOL with MATLAB Use this application for running COMSOL with LiveLink™ *for* MATLAB®. This application is only available if you have a LiveLink™ *for* MATLAB® license.

- ⚠ The COMSOL with MATLAB application requires that you use the X11 application together with MATLAB. The X-Windows application OroborOSX is not supported. On Mac OS X 10.6 Snow Leopard you need to quit the Terminal application prior to running the COMSOL with MATLAB application.

COMSOL Multiphysics Server This application launches the Terminal application and starts a COMSOL Server in a terminal window.

COMSOL Updates This application checks for available product updates on www.comsol.com.

- ⚠ The COMSOL applications do not work if moved outside the COMSOL folder. Create an alias if, for example, a desktop icon is required.


Running COMSOL from a Terminal Window

COMSOL can also be launched from a terminal window using the shell script `COMSOL44/bin/comsol`.

To run the `comsol` command more easily, include the `COMSOL44/bin` directory in the path or make a symbolic link from `/usr/bin/comsol` to the `comsol` script. Those with administrator privileges can create a symbolic link with the command

```
sudo ln -s /Applications/COMSOL44/bin/comsol /usr/bin/comsol
```

(assuming COMSOL is installed in the Applications folder). This command asks for a password before creating the link.

 The `comsol` command must not be moved from the `COMSOL44/bin` folder. The COMSOL applications also use this script.


RUNNING A CLASSKIT LICENSE

To start COMSOL using a Classkit License, start COMSOL from the terminal window using the `-ckl` option, for example,

```
comsol -ckl
```

Running COMSOL in Client-Server Mode

When you start COMSOL by, for example, launching the COMSOL Multiphysics application, COMSOL is run as a single application that includes the functionality of both the COMSOL Client and COMSOL Server, as explained later in this section. However, the COMSOL Client/Server architecture lets you access the COMSOL Server—the COMSOL computational engine—as a separate process. For example, the COMSOL Desktop can act as a COMSOL Client when connected to a COMSOL Server.

 The license server is not the same as a COMSOL server. The license manager can run on a computer different from both the ones used by COMSOL Desktop and COMSOL Server.

You need a Floating Network License to run the COMSOL Server and the COMSOL Client on separate computers. However, any COMSOL license is sufficient for running the Client and the Server on the same computer.

The Client and Server need not run on the same platform. For example, you can run the COMSOL Desktop on Mac connecting to a COMSOL Server on a Windows or Linux computer. This enables offloading heavy-duty computations

from your personal laptop or desktop to run just the COMSOL Desktop graphical user interface. A typical use would be to run the COMSOL Server on a computer with large amounts of memory (RAM) and processing power and to use your personal computer for pre- and postprocessing with the COMSOL Desktop.


STARTING A COMSOL SERVER

To start the COMSOL Server, run the COMSOL Server application. A terminal window appears asking you for a username and password. You can use any username and password of your choice, it is only used for connecting a COMSOL Client with a COMSOL Server.

When the COMSOL Server starts, it listens for a COMSOL Client connection on the port listed in the command window.


Connecting a COMSOL Client to a COMSOL Server

You can start a COMSOL Client session from the COMSOL Desktop by selecting **Connect to Server** from the **File** menu in the COMSOL Desktop. When you start the Client, a Connect to Server window appears prompting you for a computer name (Server) where the COMSOL Server is running, Port number, Username, and Password.



Once you have filled out this information and clicked **OK**, the COMSOL Server terminal window displays information that a COMSOL Client has connected. For more information on running COMSOL in Client/Server mode, see the *COMSOL Multiphysics Reference Manual*.

Running COMSOL in Batch Mode

You can submit COMSOL batch jobs from the COMSOL Desktop and the command line. To run a COMSOL batch job, you need to make the Batch feature visible: in the Model Builder tree, click the **Show** button () and select **Advanced Study Options**. In the Model Builder, right-click a **Study** node and select **Batch** to

create batch jobs. From the terminal window, you can start batch jobs using the `comsol batch` command. This is an example of how such a command could look:

```
comsol batch -inputfile in.mph -outputfile out.mph
```

To run a specific study add the command line option `-study <tag>`, where `<tag>` is the tag of the study to run, for instance, `std1`. To see the tag, select **Model Builder Node Label>Show Name and Tag** in the COMSOL Desktop (on the Home toolbar in Windows, or from the Windows menu for Linux and Mac).

The *COMSOL Multiphysics Reference Manual* includes a dedicated section on running COMSOL from the terminal window, including a list of COMSOL commands and associated syntax.

Running COMSOL on Multicore Computers

COMSOL supports two modes of parallel operation: shared-memory parallel operations and distributed-memory parallel operations, including cluster support for Windows and Linux. This section covers shared-memory processing, or multithreading, which is important for the performance of COMSOL computations. Some terms that are frequently used in when describing multithreading are:

- *Core*: The core is a processor core used in shared-memory parallelism by a computational node with multiple processors.
- *Speedup* is how many times faster a job runs on N cores compared to 1 core, on a specific compute node. The speedup depends on the simulation type, the hardware used, and hardware drivers used.

On Mac OS X, the default number of processor cores used by COMSOL is the total number of available physical cores. For example, if you have a 2 x dual core machine, 4 cores are used in parallel by a COMSOL process.

SHARED-MEMORY OPTIONS


From the terminal window, use the `comsol` command option `-np` to control the number of cores and processors used. The default is to use all available cores and processors. For example:


```
comsol -np 2
```

launches COMSOL using 2 cores (if available).

You can experiment to find the options that work best for your configuration. For more information see the *COMSOL Multiphysics Reference Manual*.

Running COMSOL on Clusters

You can launch COMSOL cluster jobs from the COMSOL Desktop and the command line. To run COMSOL on a cluster, you need to make the cluster feature visible: in the Model Builder tree, click the **Show** button () and select **Advanced Study Options**. Then in the Model Builder, right-click a **Study** node and select **Cluster Computing** or **Cluster Sweep** to create cluster jobs. Cluster computing requires a Floating Network License.

-  COMSOL cannot be run on a cluster running Mac OS X; however, you can use the Cluster Computing or Cluster Sweep feature to connect to a Windows or Linux cluster.

A tutorial model for cluster testing is included in the Model Libraries window under **COMSOL Multiphysics>Tutorial models>micromixer_cluster**.

For more information about how to run COMSOL in parallel on clusters, see the *COMSOL Multiphysics Reference Manual*. For installation on Clusters, see “Cluster Installation” on page 32 for Windows and “Cluster Installation” on page 78 for Linux.

Running COMSOL on the Cloud

COMSOL supports cloud computing using Linux through Amazon Elastic Compute Cloud™ (Amazon EC2)™. See the PDF version of *Running COMSOL on the Amazon™ Cloud* for further information: www.comsol.com/ec2_manual.

Installing on Linux

INSTALLATION OVER THE INTERNET

Installation of any paid-for license on Linux requires a license file, which is sent to you by your COMSOL representative by email. To be able to generate the license file, information about your hardware is needed in the form of a *hostid* (host ID). The *hostid* is used to lock the license to your hardware and needs to be sent by you to a COMSOL representative prior to the license file being generated.



A trial license can be given to you with the intention to test the software without any payment obligation for noncommercial or nonproduction use. This option is not available in all regions. For installation of a Single User Trial License on Linux, you can follow the same instructions as for a paid-for license.

Obtaining the Hostid

Follow these steps to obtain a *hostid*:

- 1 Start a Terminal window.
- 2 Enter `/sbin/ifconfig eth0`

This displays the Ethernet address (also called a MAC address) which consists of six bytes displayed as six pairs of hexadecimal digits such as 00:40:05:16:E5:25.

Obtaining the Host Name

If you have been informed by a COMSOL representative that you need to run the FlexNet license manager for your installation, then you also need the Host Name:

- 1 To get the Host Name, start a Terminal window.
- 2 Enter `hostname` at the terminal prompt.

If your network administrator prefers to use a fixed IP address for this particular computer, this IP Address can be optionally used in place of the Host Name. For more information on license manager installation see [“License Manager Installation on Linux” on page 80](#).

Obtaining the License File from a COMSOL Representative

Send the *hostid* information, as well as Host Name, if applicable, in an email to your COMSOL representative, who will respond by email with an attached license file (`license.dat`). Save this file to any location on your computer. You need to refer to it during installation. A trial license file for Linux cannot normally be edited or changed in any way by the user but has to be identical to the one sent to you by a COMSOL representative. However, if you were sent a license file that


requires a license manager, then minor edits are required. For information on the type of license file required for installations using a license manager, see “[The License File](#)” on page 35.

Registering with COMSOL Access

Once you have saved your license file, follow these steps to register or login to COMSOL Access and to start the installation:

- 1 Click the link for downloading the software as given in the software download email from your COMSOL representative. This link is identical or similar to: www.comsol.com/product-download
- 2 If you haven't already created a COMSOL Access account, you will be prompted to create it. While creating the account, point to your license file (`license.dat`) to associate it with your account information.
If you already created a COMSOL Access account, then you can associate the license file on the COMSOL Access page with your account under Manage Licenses at www.comsol.com/access/licenses
- 3 Continue with the instructions in the next section Downloading the COMSOL Installer.

DOWNLOADING THE COMSOL INSTALLER

- 1 Go to the web page www.comsol.com/product-download.
 - 2 Select installation for **Linux 32-bit** or **Linux 64-bit**.
 - 3 You are now given the option of installing COMSOL using the **Online Installer**. (For the DVD option see “[Installation from Downloaded DVD Image](#)” on page 11.) In addition, there are two further options of Compact Installation or Full Installation:
 - **Compact Installation:** Includes the on-line documentation. The model library tutorials are stripped of solutions, which reduces download time. The size of this download ranges from 600 MB to 1.6 GB depending on your license.
 - **Full Installation:** Includes the full documentation and the complete model library with meshes and solutions for your licensed products. The size of this download ranges from 1.0 GB to 3.7 GB depending on your license.
-  If you have problems downloading (such as **Error downloading file. Connection refused: connect**), please review this knowledge base entry: www.comsol.com/support/knowledgebase/1149. If you still have problems, please contact your local COMSOL representative or technical support from the Support Center page at www.comsol.com/support.
- 4 Selection one of the options for Compact Installation or Full Installation.

Clicking one of the install buttons starts the download of the COMSOL Installer. For Linux, the file to download is given a name depending on whether it is for 32-bit or 64-bit Linux and whether it is for a compact or full installation:

- `comsol144_compact_glnx86.zip` (Compact, 32-bit)
- `comsol144_compact_glnxa64.zip` (Compact, 64-bit)
- `comsol144_glnx86.zip` (Full, 32-bit)
- `comsol144_glnxa64.zip` (Full, 64-bit)

STARTING THE INSTALLER FOR INSTALLATION OVER THE INTERNET

The COMSOL Installer is a user interface tool that guides you through the installation process. Start the COMSOL Installer by first unzipping the downloaded file and then running the setup script. The COMSOL 4.4 Installer window should now appear. Now continue with the instructions in the section “[Running The COMSOL Installer](#)” on page 75.

Installation from Downloaded DVD Image

Installation from a DVD where the DVD image is downloaded from COMSOL for off-line installation requires you to first create a COMSOL Access account as described in the section “[Installation Over the Internet](#)” on page 7.

- 1 Once you are logged in to COMSOL Access, you are now given the option of installing COMSOL using the **Online Installer** or to download the **DVD Image for Offline Installation**. This section covers the DVD Image option. In addition, there are two further options of Compact Installation or Full Installation:
 - **Compact Installation:** Includes the on-line documentation. The model library tutorials are stripped of solutions, which reduces download time. The size of this download ranges from 600 MB to 1.6 GB depending on your license.
 - **Full Installation:** Includes the full documentation and the complete model library with meshes and solutions for your licensed products. The size of this download ranges from 1.0 GB to 3.7 GB depending on your license.



If you have problems downloading (such as **Error downloading file. Connection refused: connect**), please review this knowledge base entry: www.comsol.com/support/knowledgebase/1149. If you still have problems, please contact your local COMSOL representative or technical support from the Support Center page at www.comsol.com/support.

- 2 In the section for the DVD Image option, click one of the buttons for **Compact DVD Download** or **Full DVD Download**. Clicking one of the install buttons starts the download of the COMSOL DVD Image. The file to download is called `COMSOL44_dvd.iso`.
- 3 When you have downloaded the DVD image, burn the DVD image to a disc. Use a DVD burning tools or command such as `cdrecord` to burn the DVD. Alternatively, directly mount the DVD using a loopback device:

```
mount -o loop COMSOL44_dvd.iso /mnt
```

Starting the Installer from Downloaded DVD Image

This section applies if you have burnt a DVD image downloaded from COMSOL for off-line installation.

STARTING THE INSTALLER FROM A DOWNLOADED DVD IMAGE

The COMSOL Installer is a user interface tool that guides you through the installation process. To start the installer:

- 1 Make sure the COMSOL DVD is in the DVD drive (or mount the image).
- 2 Type `/mnt/setup`
- 3 The COMSOL 4.4 Installer window appears. Now continue with the instructions in the section [“Running The COMSOL Installer” on page 75](#).

Installation from DVD

This section applies if you have received a DVD from a COMSOL representative.

STARTING THE INSTALLER FROM A DVD

The COMSOL Installer is a user interface tool that guides you through the installation process. To start the installer:

- 1 Insert the COMSOL 4.4 DVD into the DVD drive.
- 2 If the DVD is not mounted automatically by your operating system, use the `mount` command to mount it.
- 3 To start the installation, enter the command

```
sh drivepath/setup
```

where *drivepath* is the mount point of the DVD drive, for example `/media/cdrom`.

You might have to mount the DVD with the option `-o exec` if your Linux mounts the DVD without execute options by default.

The COMSOL 4.4 Installer window appears. Now continue with the instructions in the section [“Running The COMSOL Installer”](#) on page 75.

Installation from USB Flash Drive

This section applies if you have received a USB Flash Drive from a COMSOL representative.

STARTING THE INSTALLER FROM A USB FLASH DRIVE

The COMSOL Installer is a user interface tool that guides you through the installation process. To start the installer:

- 1 Connect the USB Flash Drive to your computer.
- 2 If the USB Flash Drive is not mounted automatically by your operating system, use the mount command to mount it.
- 3 To start the installation, enter the command

```
sh drivepath/setup
```

where *drivepath* is the mount point of the USB Flash Drive, for example `/media/usb`.

You might have to mount the USB Flash Drive with the option `-o exec` if your Linux mounts the USB Flash Drive without execute options by default.

- 4 The COMSOL 4.4 Installer window appears. Now continue with the instructions in the section [Running The COMSOL Installer](#) below.

Running The COMSOL Installer

The steps for running the COMSOL Installer are independent of the installation media option you used. If you have followed the above instructions, the

COMSOL Installer should now appear. For a detailed description and screen shots of the different COMSOL Installer steps, see the instructions for Windows in the section “[Running the COMSOL Installer](#)” on page 13. The procedure for running the COMSOL Installer on Linux is similar and summarized below with the differences from installation on Windows highlighted:

- 1 When the installer window appears, click **New Installation**.
- 2 Read the license agreement, select **I accept the terms of the license agreement**, specify **License information**, and then click **Next**.
- 3 If you have a Named Single User License and you are installing the software on the license server, a dialog box opens up and you are asked to enter the user to bind the license to.
- 4 Select for which platforms (32-bit or 64-bit Linux) that you wish to install and click **Next**.
- 5 Select the features to install and specify the path to the COMSOL installation directory.
- 6 Click **Next**.
- 7 If you have licensed LiveLink™ for MATLAB®, then specify the MATLAB root folder.
- 8 Click **Next**.
- 9 Click **Install** to start the installation.
- 10 When the installation process is finished, the **Finish** window appears. If errors arose during installation, this window issues a notification. The installer also writes a log entry into the text file `comsolsetup.log`, which resides in the specified installation directory. Click **Finish** to quit the installer. If you installed from DVD, use the `umount` and `eject` commands to unmount and eject the DVD. Some Linux configurations automatically unmount and eject the DVD when you press the DVD drive button.
- 11 To make sure all users can easily start COMSOL, include the `comsol144/bin` directory in all users’ paths or make a symbolic link from `/usr/local/bin/comsol` to the `comsol` command (see the `Linux ln` command).

Web Browser for Viewing the Documentation

The file browser in the bin directory attempts to start common web browsers that are available with the supported Linux versions. Edit the file in any text editor to adjust it for your preferred web browser. The variable `BROWSERS` in this file contains

a list of web browsers in order of preference. If you want to make a specific browser the preferred web browser, put it first in the list.

Automated Installation

You can install COMSOL using an automated installation process with minimal user interaction. This method requires installation from DVD or DVD image. The documentation on how to create an answer file is available in the template, `setupconfig.ini`, which is available on the DVD. When you have created an answer file, start the installation by running

```
<path to DVD>/setup -s <answer file path>
```

where `<answer file path>` is the path to your answer file.

Removing (Uninstalling) the COMSOL Installation

The COMSOL 4.4 installation adds files only in the `comsol44` directory. To remove the COMSOL installation, simply delete the `comsol44` directory including all subdirectories.

Product Updates and Model Library Update

COMSOL periodically releases product updates with improvements and corrections to reported problems. By default, COMSOL checks for updates at startup. You can turn this feature on and off from the COMSOL Desktop Preferences Window. Here you can also configure settings for the Model Library Update.

The COMSOL Model Library is updated on a regular basis by COMSOL. To open the Model Library Update window from the File>Help menu (Windows users) or from the Help menu (Mac and Linux users), select Update COMSOL Model Library.

This connects you to the COMSOL Model Update website where you can access the latest models and model updates. This includes models that have been added or improved since the latest product release.

Using the Updates section in the Preferences dialog box, which you open from the COMSOL Desktop, you can configure proxy server settings as well as model and documentation directories for the Model Library Update. See the *COMSOL Multiphysics Reference Manual* for more information including command-line options for the Model Libraries.

Changing the Path to the MATLAB® Installation

You can change the path to the MATLAB installation in the **Preferences** window accessed from the **Options** menu of the COMSOL Desktop. For more information, see the LiveLink™ for MATLAB® documentation.

Cluster Installation

COMSOL supports two modes of parallel operation: shared-memory parallel operations and distributed-memory parallel operations, including cluster support. This section is dedicated to distributed-memory parallel installation.

COMSOL can distribute computations on compute clusters using the MPI model. One large simulation can be distributed across many compute nodes. Also, parametric sweeps can be done with individual parameter cases distributed to each cluster node.

SYSTEM REQUIREMENTS

The installation instructions above can also be followed for clusters. COMSOL supports shared-memory parallelism and distributed-memory parallelism on 32-bit and 64-bit Linux. For details on system requirements, see www.comsol.com/system-requirements.

LICENSE MANAGER

COMSOL requires a Floating Network License for running on clusters. Please check the license file for the CLUSTERNODE feature, which needs to be present

to enable the cluster computing functionality. The license manager needs to be accessible from all nodes in the cluster. Therefore it is often a good idea to have it run on the head node.

INSTALLATION FOLDER

The COMSOL installation folder should be shared between all compute nodes and the head node.

FEATURES

During installation, make sure the Cluster Components feature is selected.

ACCESS TO CLUSTER

If you work on a computer that is not on the cluster, install COMSOL on that computer. Typically, you use a scheduler to launch jobs on the cluster. Make sure the scheduler client software is installed on that computer. You can configure the installation to use the scheduler by changing the `comsol.ini` file according to the section on MPI Options in the *COMSOL Multiphysics Reference Manual*.

For more information on installing and running COMSOL on clusters, see [“Running COMSOL on Clusters” on page 88](#) and the *COMSOL Multiphysics Reference Manual*.

License Manager Installation on Linux

You do not need to install the license manager if you are installing a trial version. The paid-for version on Linux, however, always requires a running license manager. Many of the instructions for installing the FlexNet license manager are similar to those for Windows. This section covers only the differences when installing on Linux. For general information on the license manager software, see “[License Manager Installation on Windows](#)” on page 33.


FlexNet License Manager Software Components

The license manager consists of the following software components:

- License manager daemon (`lmgrd`)
- Vendor daemon (`LMCOMSOL`)
- FlexNet utility program (`lmutil` and others)

The two daemons (`lmgrd` and `LMCOMSOL`) run on the license server. When a user starts COMSOL on a client computer, communication is established through the network from the client to the license server and the license manager daemon (`lmgrd`). That daemon in turn makes a request to the vendor daemon (`LMCOMSOL`), which releases licenses according to information in the `license.dat` file. The FlexNet utility programs are used to handle license server management tasks.

FlexNet License Manager Documentation

For detailed information on the FlexNet license manager software, click the  button (File menu) and choose Help>Documentation (Windows) or select Help>Documentation (Mac and Linux) and scroll to the bottom of the page to locate a PDF copy of the *FlexNet License Administration Guide*.

The License File

The license file for use on Linux is identical to that for Windows, except in the case of a Named Single User License, which is described below. See [“The License File” on page 35](#) for general license file information.

LICENSE FILES FOR NAMED SINGLE USER LICENSE

If you have a Named Single User License the installer automatically creates an options file that binds the license to the named user. This section describes the format of the options file and how the `license.dat` file points to the options file.

Below is an example of an options file, `LMCOMSOL.opt`, for a user “philip” who has access to COMSOL Multiphysics, the Structural Mechanics Module, and the CAD Import Module. Notice that to access COMSOL Multiphysics, the options file must include both the `COMSOL` and the `COMSOLGUI` features:

```
INCLUDE COMSOL USER philip
INCLUDE COMSOLGUI USER philip
INCLUDE CADIMPORT USER philip
INCLUDE CADREADER USER philip
INCLUDE STRUCTURALMECHANICS USER philip
```

Each `INCLUDE` row in the `LMCOMSOL.opt` file has a corresponding `FEATURE` row in the `license.dat` file (with the `USER_BASED` keyword). The second item on each `FEATURE` row is the name of the feature for which you have a license.

For more information on which `FEATURE` items are available, see [“The License File” on page 35](#).

The `license.dat` file needs to point to the options file. The path to the options file is indicated by the `options` keyword. If your options file is placed here:

```
/usr/local/comsol44/license/LMCOMSOL.opt
```

then the `VENDOR` row in `license.dat` should read

```
VENDOR LMCOMSOL port=1719 options=/usr/local/comsol44/license/LMCOMSOL.opt
```

Installing the License Manager

The FlexNet license manager is automatically installed when installing COMSOL unless otherwise specified on the Features page of the COMSOL Installer; see [“Features Page” on page 19](#). The check box for the license manager components can be found last in the list of software components.

If you want to install COMSOL on the same computer as the license manager, first perform a complete COMSOL installation including the license manager software components. When finished, skip the remainder of this section and continue with [Starting the License Manager](#) below.

To install only the license manager, follow the installation instructions for COMSOL earlier in this document and on the Features page, clear all check boxes except the one for the license manager.

AUTOMATED LICENSE MANAGER INSTALLATION

Alternatively, the license manager can be installed using an automated installation process with minimal user interaction, see [“Automated Installation” on page 77](#). Set `licmanager = 1` in the answer file to install the license manager.

Starting the License Manager

You can start the license manager manually or it can run automatically at boot.

STARTING THE LICENSE MANAGER MANUALLY

To start the license manager manually, make the `license/$arch` directory the current directory and enter

```
./lmgrd -c ../license.dat -l /var/tmp/comsol144.log
```

The server is now ready to distribute licenses over the network. It writes any debug information to the log file `/var/tmp/comsol144.log`.

STARTING THE LICENSE MANAGER AUTOMATICALLY AT BOOT

In order for the license manager to start automatically at boot, you need to add Bourne shell commands to the appropriate boot script. You must be a superuser (root) to edit boot scripts.



For security reasons, it is recommended that the daemons are not started as root. Instead, use a dedicated username to start the license manager.

The procedure for editing boot scripts on each platform appears in the following table:

PLATFORM	PROCEDURE
SuSe Linux	<p>The following instructions should work for SuSE Linux distributions, where \$arch is either glnx86 (32-bit Linux), or glnxa64 (64-bit Linux).</p> <p>In the comsol44/license/\$arch directory, enter the commands</p> <pre>cp rc.lm /etc/init.d/comsol44lm chmod 755 /etc/init.d/comsol44lm</pre> <p>Edit /etc/init.d/comsol44lm, replacing dir with the full path to the \$arch platform directory, and replace username with an actual username.</p> <p>Now create the following link</p> <pre>cd /etc/init.d/rc5.d ln -s ../comsol44lm S91comsol44lm</pre>
Debian Linux	<p>The following instructions should work for Debian Linux distributions, where \$arch is either glnx86 (32-bit Linux), or glnxa64 (64-bit Linux).</p> <p>Copy the file comsol44/license/\$arch/lm_comsol to /etc/init.d</p> <p>Edit /etc/init.d/lm_comsol. Update the FP and MYUSER variables as indicated in the file. Use the utility update-rc.d to automatically update the system's init script links:</p> <pre>update-rc.d lm_comsol start 99 2 3 4 5 . stop 1 0 1 6 .</pre> <p>This means that the COMSOL license manager is started by runlevels 2, 3, 4, and 5, and stopped by runlevels 0, 1, and 6. Enter man update-rc.d for more information on init scripts.</p>
Linux, General	<p>The following instructions should work for most Linux distributions, where \$arch is either glnx86 (32-bit Linux) or glnxa64 (64-bit Linux).</p> <p>Copy the file comsol44/license/\$arch/rc.lm and paste it at the end of /etc/rc.d/rc.local.</p> <p>Replace dir in the code fragment with the full path to the \$arch platform directory, and replace username with an actual username.</p>

Verifying that the License Manager is Running

Once you start the license manager, it is good practice to verify that the license manager processes are running. Use administrative commands such as **top** or **ps** to check that both the vendor daemon (LMCOMSOL) and the license manager (lmgrd) are running.

Starting COMSOL

After the installation is complete and the license manager daemons are running on the license server, you can start using COMSOL. For more information on how to run COMSOL, see [“Running COMSOL on Linux” on page 85](#).

Changing the License

If you have received a new license file—for example, when adding COMSOL products to an existing license—replace the current license file with the new one. Double-check the contents of this file to make sure it lists the products that the license includes.



When the license file has been changed, you must restart the license manager; otherwise, it continues to use the old license file still in memory.

RESTARTING THE LICENSE MANAGER

To restart the license manager, make the `license/$arch` directory under the COMSOL installation directory the current directory, then enter the following commands:

```
./lmdown -c ../license.dat
./lmgrd -c ../license.dat -l /var/tmp/comsol144.log
```

OBTAINING A HOSTID

If COMSOL is already installed on your license server, you can determine the hostid by executing the `lmhostid` command

```
comsol144/license/$arch/lmhostid
```

where `$arch` is `glnx86` (32-bit Linux) or `glnxa64` (64-bit Linux).

Troubleshooting License Errors

If you have questions or problems with your installation, see [“Troubleshooting License Errors” on page 91](#).

Running COMSOL on Linux

Running COMSOL

If you are running a Linux version with a graphical desktop environment, you might find a COMSOL Multiphysics icon that you can simply click to start COMSOL. Alternatively, using a terminal window, you can run the `comsol` command. If it is not available, ask your system manager to make it available to you, or, if you have administrative privileges on your Linux system, add the `comsol` command to the search path. The `comsol` command is located in the `bin` folder in the COMSOL installation directory. This is a typical example of a command that adds `comsol` to the search path is (assuming you are logged in as `root`):

```
ln -s /usr/local/comsol144/bin/comsol /usr/bin/comsol
```

Running COMSOL on Multicore Computers

COMSOL supports two modes of parallel operation: shared-memory parallel operations and distributed-memory parallel operations, including cluster support for Windows and Linux. This section covers shared-memory processing, or multithreading, which is important for the performance of COMSOL computations. Some terms that are frequently used in when describing multithreading are:

- *Core*: The core is a processor core used in shared-memory parallelism by a computational node with multiple processors.
- *Speedup* is how many times faster a job runs on N cores compared to 1 core, on a specific compute node. The speedup depends on the simulation type, the hardware used, and the hardware drivers used.

On Linux, the default number of processor cores used by COMSOL is the total number of available physical cores. For example, if you have a 2 x dual core machine, 4 cores are used in parallel by a COMSOL process.

SHARED-MEMORY OPTIONS


From the Terminal window, use the `comsol` command option `-np` to control the number of cores and processors used. The default is to use all available cores and processors. For example:

```
comsol -np 2
```

launches COMSOL using 2 cores (if available).

You might need to experiment to find the options that work best for your configuration. For more information see the *COMSOL Multiphysics Reference Manual*.

Running COMSOL in Batch Mode

You can submit COMSOL batch jobs from the COMSOL Desktop and the command line. To run a COMSOL batch job, you need to make the Batch feature visible: in the Model Builder tree, click the **Show** button () and select **Advanced Study Options**. In the Model Builder, right-click a **Study** node and select **Batch** to create batch jobs. From a terminal window, you can start batch jobs using the `comsol batch` command. This is an example of such a command:

```
comsol batch -inputfile in.mph -outputfile out.mph
```

To run a specific study add the command-line option `-study <tag>`, where `<tag>` is the tag of the study to run, for instance, `std1`. To see the tag, select **Model Builder Node Label>Show Name and Tag** in the COMSOL Desktop (on the Home toolbar in Windows, or from the Windows menu for Linux and Mac).

The *COMSOL Multiphysics Reference Manual* has a dedicated section on running COMSOL from a terminal window, including a list of COMSOL commands and associated syntax.

Running COMSOL in Client-Server Mode

When you start COMSOL by, for example, entering the `comsol` command with no additional arguments, COMSOL is run as a single application that includes the functionality of both the COMSOL Client and COMSOL Server, as explained later in this section. However, the COMSOL Client/Server architecture lets you access the COMSOL Server—the COMSOL computational engine—as a separate

process. For example, the COMSOL Desktop can act as a COMSOL Client when connected to a COMSOL Server.



The license server is not the same as a COMSOL Server. The license manager can run on a computer different from both the ones used by COMSOL Desktop and COMSOL Server.

You need a Floating Network License to run the COMSOL Server and the COMSOL Client on separate computers. However, any COMSOL license is sufficient for running the Client and the Server on the same computer.

The Client and Server need not run on the same platform. For example, you can run the COMSOL Desktop on Windows connecting to a COMSOL Server on a Linux computer. This enables offloading heavy-duty computations from your personal laptop or desktop to run just the COMSOL Desktop graphical user interface. A typical use would be to run the COMSOL Server on a computer with large amounts of memory (RAM) and processing power and to use your personal computer for pre- and postprocessing with the COMSOL Desktop.

STARTING A COMSOL SERVER

To start the COMSOL Server from a terminal window, run the `comsol` command with the `server` argument:

```
comsol server
```

You are then prompted for a username and password. You can use any username and password of your choice, it is only used for connecting a COMSOL Client with a COMSOL Server.


When the COMSOL Server starts, it listens for a COMSOL Client connection on the port listed in the command window.

Connecting a COMSOL Client to a COMSOL Server

You can start a COMSOL Client session from the COMSOL Desktop by selecting Connect to Server from the File menu in the COMSOL Desktop. You can also start a COMSOL Client session from a terminal window by running the `comsol` command with the `client` argument:

```
comsol client
```

When you start the Client, a Connect to Server window appears prompting you for a computer name (Server) where the COMSOL Server is running, Port number, Username, and Password:




Once you have filled out this information and clicked **OK**, the COMSOL Server terminal window displays information that a COMSOL Client has connected. For more information on running COMSOL in Client/Server mode, see the *COMSOL Multiphysics Reference Manual*.

Running a Classkit License

To start COMSOL using a Classkit License, start COMSOL using the `-ck1` option:

```
comsol -ck1
```

Running COMSOL on Clusters

You can launch COMSOL cluster jobs from the COMSOL Desktop and the command line. To run COMSOL on a cluster, you need to make the cluster feature visible: in the Model Builder tree, click the **Show** button () and select **Advanced Study Options**. Then in the Model Builder, right-click a **Study** node and select **Cluster Computing** or **Cluster Sweep** to create cluster jobs. Cluster computing requires a Floating Network License.

The following terms occur frequently when describing the hardware for cluster computing and shared memory parallel computing:

- **Compute node:** The compute nodes are where the distributed computing occurs. Each distributed COMSOL process resides in a compute node and

communicates with other compute nodes using MPI (message-passing interface).

- **Host:** The host is a physical machine (hardware) with a network adapter and unique network address. The host is part of the cluster. It is sometimes referred to as a physical node.
- **Core:** The core is a processor core used in shared-memory parallelism by a computational node with multiple processors.

The number of used hosts and the number of computational nodes are usually the same. For some special simulation types, like very small simulations with many parameters, it might be beneficial to use more than one computational node on one host.

A tutorial model for cluster testing is included in the Model Libraries window under **COMSOL Multiphysics>Tutorial models>micromixer_cluster**.

QUICK TROUBLESHOOTING

- Your first step is to make sure you have the latest release installed. Check that you have COMSOL 4.4 or later and make sure to install the latest product updates.
- If you get the error message **Process status indicates that process is running**, then cancel any running jobs in the scheduler that you use. In the COMSOL Desktop, locate the **External Process** page at the bottom right. Click the **Clear Status** button.

For more information about how to run COMSOL in parallel on Linux clusters, see the *COMSOL Multiphysics Reference Manual*. For installation on Clusters, see “[Cluster Installation](#)” on page 78.

Running COMSOL on the Cloud

COMSOL supports cloud computing using Linux through Amazon Elastic Compute Cloud™ (Amazon EC2)™. See the PDF version of *Running COMSOL on the Amazon™ Cloud* for further information: www.comsol.com/ec2_manual.

Running COMSOL with MATLAB

Running COMSOL with MATLAB starts a COMSOL Server and a MATLAB Desktop. No COMSOL graphical user interface is involved. For a tutorial, see the *LiveLink for MATLAB User's Guide*.

To launch MATLAB and connect it to a COMSOL Server, run the command

```
comsol server matlab
```

STARTING COMSOL WITH MATLAB USING THE GRAPHICS SERVER

To display the plot in a COMSOL graphics window you need to run COMSOL with MATLAB using the graphics server. To do so, start COMSOL with MATLAB from a terminal window with the `-graphics` flag:

```
comsol server matlab -graphics
```

REQUIRED PROGRAMS FOR RUNNING COMSOL WITH MATLAB

The `xterm` program is necessary for the command `comsol server matlab`. The `ssh` program is needed to call MATLAB functions from COMSOL.

- To install the missing packages on Debian and Ubuntu, type

```
sudo apt-get install xterm ssh
```
- To install the missing packages on RedHat Enterprise and Fedora, type

```
sudo yum install xterm tcsh
```
- To install the missing packages on OpenSUSE, type

```
sudo zypper install xterm tcsh
```

Troubleshooting License Errors

If you have questions or problems with your installation, start by checking the COMSOL Support Knowledge Base at www.comsol.com/support/knowledgebase/ for up-to-date information about installation and license issues. If this does not help, then please contact COMSOL technical support at support@comsol.com.

THE COMSOL SUPPORT KNOWLEDGE BASE

The most important Knowledge Base entries for installation questions and license errors are the following:

SUBJECT	KNOWLEDGE BASE ENTRY
Could not obtain license for COMSOL Multiphysics GUI	www.comsol.com/support/knowledgebase/903
Running COMSOL in parallel on clusters	www.comsol.com/support/knowledgebase/1001
Updating the COMSOL License Manager	www.comsol.com/support/knowledgebase/1022
COMSOL Installation Companion	www.comsol.com/support/knowledgebase/1077
Error: An error has occurred. See the log file C:\Users...	www.comsol.com/support/knowledgebase/1083
Selecting hardware for clusters	www.comsol.com/support/knowledgebase/1116
The COMSOL 4.4 tab is not available in the Microsoft Excel ribbon	www.comsol.com/support/knowledgebase/1147
Error: Error downloading file. Connection refused: connect	www.comsol.com/support/knowledgebase/1149

You can also view videos about installation at: www.comsol.com/video/browse/installation.

LICENSE ERRORS

This section summarizes the most common post-installation error messages generated by COMSOL, and it gives some advice how to troubleshoot them. For a complete list of error messages, see the FlexNet license manager documentation. This documentation is shipped with your COMSOL installation; see “FlexNet®

[License Manager Documentation](#)” on page 34 on where to find it.

If you need to review the license manager log file, or send it to COMSOL technical support, this is where you usually find it (depending on choices you made during the installation):

- Windows: C:\Program Files\COMSOL44\license\comsol44.log
- Mac OS X: /var/tmp/comsol44.log
- Linux: /var/tmp/comsol44.log

If you need to access the license file, this is where you usually find it:

- Windows: C:\Program Files\COMSOL44\license\license.dat
- Mac OS X: /Applications/COMSOL44/license/license.dat
- Linux: /usr/local/comsol44/license/license.dat

ERROR MESSAGE	EXPLANATION
License error	A general license error has occurred. Check the error message for details that might help solve the problem. If you need help in interpreting the information, see the FlexNet License Manager documentation or send the complete error message to support@comsol.com.
License error: -1. Cannot find license file.	The license file is missing or your system settings don't allow you to read the file. Review the license manager installation steps above and check that you have administrative rights on your computer.
License error: -2. Invalid license file syntax.	There is a formatting problem with your license file. This can happen if you edit it with a word processing software such as Microsoft Word which inserts extra (invisible) characters. Use a plain text editor instead (on Windows: Notepad, WordPad, or similar). Formatting problems can also happen if the file is corrupted while being copied or emailed from one computer to another.
License error: -4. Licensed number of users already reached.	The license manager has detected that all available licenses of a certain COMSOL product have been used by other users. Contact your license administrator and report this problem. You might need more licenses of one of the add-on products.
License error: -5. No such feature exists.	The license manager has encountered a problem during startup. Check the license manager log file for error messages. Please send the log file to support@comsol.com if you want help in interpreting the information. NOTE: The license manager creates the log file. If there is no log file, make sure to first start the license manager. Please refer to one of the License Manager Installation sections of this manual for instructions how to install and start the COMSOL license manager.

ERROR MESSAGE	EXPLANATION
License error: -10. Feature has expired.	This error message indicates that you have a time-limited (trial) license and that your license has expired. Contact your license administrator to see if a more recent license file is available. You can also contact a COMSOL representative to renew your time-limited license.
License error: -12. Invalid returned data from license server system.	<p>Check that no firewall on the COMSOL client is preventing the connection from the COMSOL client to the license server. Temporarily disable any firewall on the COMSOL client to see if that helps.</p> <p>Check that no firewall on the license server is preventing the connection from the COMSOL client computer to the license manager, or the connection from the lmgrd daemon and the LMCOMSOL daemon.</p> <p>If the problems remain, send the license manager log file to support@comsol.com.</p>

ERROR MESSAGE	EXPLANATION
<p>License error: -15. Cannot connect to license server system.</p>	<p>The COMSOL license manager has not been installed or started yet. If the first line of your license.dat file looks like this:</p> <pre style="text-align: center;">SERVER mylicserver 000123456789 1718</pre> <p>a license manager is required. Please refer to the License Manager Installation sections of this manual for instructions on how to install and start the COMSOL license manager.</p> <p>Check that no firewall on the COMSOL client is preventing the connection from the COMSOL client to the license server. Temporarily disable any firewall on the COMSOL client to see if that helps.</p> <p>Check that no firewall on the license server is preventing the connection from the COMSOL client computer to the license manager.</p> <p>Check that the license.dat file on the COMSOL client computer points to the correct license server host name. First, find the license.dat according to the instructions above.</p> <p>Check that the first line has the correct license server Host Name. For example, if your license server Host Name is apollo, the first row in the license.dat file should look like this:</p> <pre style="text-align: center;">SERVER apollo 000123456789 1718</pre> <p>If the COMSOL client computer does not recognize apollo as a proper Host Name, it might help to instead use the fully qualified domain name (apollo.thecompany.com) or the IP address. If neither of these work, there might be a problem with DNS or the HOSTS file on the client. Please ask your system administrator for advice on how to connect with TCP/IP to the license server.</p> <p>Finally, the license manager might have encountered a problem during startup. Check the license manager log file for error messages.</p> <p>NOTE: The log file is created by the license manager after it has been started.</p> <p>Please send the log file to support@comsol.com if you want help in interpreting the information.</p>
<p>License error: -39. User/host not on INCLUDE list for feature.</p>	<p>The error means that your username does not match the one listed in the license-manager options file, LMCOMSOL.opt. To get access to COMSOL, ask your license/system administrator for help. When the username in the options file is changed, the license manager must be shut down and restarted to give the new user immediate access to COMSOL.</p>

ERROR MESSAGE	EXPLANATION
License error: -88. System clock has been set back.	The software has detected that a system clock has been set back. Please make sure that your computer's clock is set to the current local time and date. If the problem remains check that there are no files on your hard drive that have a future date.
License error: -96. License server machine is down or not responding.	Please make sure that the SERVER host name in the license.dat file is valid and that the TCP/IP network connection between the application computer and the license server is working properly. This error could also indicate that your firewall is not configured properly in order to let the license manager and vendor daemon network traffic through (typically ports 1718 and 1719). It could also indicate problems with other network security settings. Contact your systems administrator for help.
License error: -97. The desired vendor daemon is down.	The license manager has encountered a problem during startup. Check the license manager log file for error messages. NOTE: The log file is created by the license manager after it has been started. Please send the log file to support@comsol.com if you want help in interpreting the information.

Index

- A**
 - add feature 15
 - AutoCAD
 - LiveLink for 29
 - Autodesk Inventor
 - LiveLink for 28
 - automated installation
 - Linux 77
 - Mac 59
 - Windows 25
 - automated license manager installation
 - Linux license server 82
 - Mac license server 62
 - Windows license server 39
- B**
 - boot script 83
 - Bourne shell commands 82
 - browser**, Linux file 76
- C**
 - change license, with COMSOL installer 15
 - changing the license
 - Linux 84
 - Mac 64
 - Windows 42
 - Classkit License
 - definition 5
 - desktop shortcuts 46
 - Linux 88
 - Mac 67
 - Windows 45
 - cluster computing
 - Linux 88
 - Mac 70
 - Windows 50
 - comment line, license file 35
 - Community Discussion Forum 6
 - compute node 50
 - COMSOL Access 6
 - COMSOL Client
 - definition 5
 - Linux, connecting 87
 - Mac 67
 - Mac, connecting 68
 - Windows 44
 - Windows, connecting 48
 - Windows, running 47
 - comsol** command, Linux 85
 - comsol** command, Mac 67
 - COMSOL Conference 6
 - COMSOL Exchange 6
 - COMSOL Server
 - floating network license, and 5
 - Linux, running 86
 - Linux, running with MATLAB 90
 - Linux, starting 87
 - Mac 66
 - Mac, running 67
 - Mac, starting 68
 - Windows 44
 - Windows, running 47
 - Windows, running with MATLAB 52
 - COMSOL Software License Agreement 3
 - COMSOL Video Center 1
 - core 50
 - CPU-Locked Single User License 4
 - Creo Parametric
 - LiveLink for 30
 - cross-platform user interface 43, 46
 - csh program 90
- D**
 - DirectX runtime binaries 20
 - dongle 6

- downloading product *l*
 - Linux, DVD 73
 - Mac 53
 - Mac, DVD 56
 - troubleshooting 91
 - Windows 7
 - Windows, COMSOL installer 10, 72
 - Windows, DVD 11
- E** errors, license 91
- Ethernet address
 - Linux 71
 - Mac 65
 - Windows 8
 - Windows, changing license and 42
- F** FEATURE line, license file 37
- FEATURE names 37
- FlexNet
 - control panel 34
 - License Administration Guide, Linux 80
 - License Administration Guide, Mac 61
 - License Administration Guide, Windows 34
 - license manager, definition 5
 - license manager, troubleshooting 91
 - license manager, Windows 33
 - management, Linux 80
 - management, Mac 61
 - management, Windows 34
 - utility program, Linux 80
 - utility program, Mac 61
 - utility program, Windows 34
- Floating Network License
 - definition 4
 - Linux, client servers and 87
 - Linux, clusters and 88
 - Linux, clusters installation and 78
 - Mac, client server and 67
 - Mac, clusters and 70
 - management software 5
 - Windows, client server and 47
 - Windows, cluster installation and 32
 - Windows, clusters and 50
 - Windows, definition 33
- H** hard disk serial number 9
- hardware address 54
- hardware lock 6
- host 50
- hostid
 - Linux, changing licenses 84
 - Linux, Internet installations 71
 - Mac, changing licenses 65
 - Mac, Internet installations 54
 - Windows, changing licenses 42
 - Windows, Internet installations 8
 - Windows, license server and 36
- I** INCREMENT line, license file 37
- installation
 - Linux 71
 - Mac 53
 - media options *l*
 - previous 2
 - Windows 7
- K** Knowledge Base *l*
 - COMSOL Access, and 6
 - troubleshooting 91
- L** License Agreement *l*
 - license agreement 3
 - license errors 91
 - license file
 - comment line 35
 - FEATURE line 37
 - FlexNet, and 5
 - INCREMENT line 37
 - Mac, obtaining 54

- SERIAL line 37
- SERVER line 36
- troubleshooting 92
- USE_SERVER line 36
- VENDOR line 36
- Windows, obtaining 9

license manager

- automated installation on Linux 82
- automated installation on Mac 62
- automated installation on Windows 39
- daemon, Linux 80
- daemon, Mac 61
- daemon, Windows 34
- files for installation, Linux 81
- files for installation, Mac 62
- files for installation, Windows 38
- installing files, Linux 81
- installing files, Mac 62
- installing files, Windows 38
- Linux, log file 82
- Linux, starting 82
- log file 40
- log file, troubleshooting 92
- Mac, log file 63
- Mac, starting 62
- Windows, log file 41
- Windows, starting 40

license server

- Linux, and 80
- Linux, client server and 87
- Mac, and 61
- Windows, and 17
- Windows, client server and 47

license, changing

- Linux 84
- Mac 64
- Windows 42

license.dat FlexNet, and 5

license.dat Linux 81

license.dat Linux, changing 84

license.dat Mac 61

license.dat Mac, changing 64

license.dat troubleshooting 92

license.dat Windows 35

license.dat Windows, FlexNet and 34

LiveLink for

- AutoCAD 29
- Autodesk Inventor 28
- Creo Parametric 30
- Pro/ENGINEER 29
- Solid Edge 31
- SolidWorks 28
- SpaceClaim 31

lmgrd.exe Linux 80

lmgrd.exe Mac 61

lmgrd.exe Windows 34

lmhostid

- Linux 84
- Mac 65

lmutil

- Windows 42

lmutil Linux 80

lmutil Mac 61

lmutil Windows 34

log file, license manager 40

log file, Linux 82

log file, Mac 63

log file, troubleshooting 92

log file, Windows 41

M MAC address

- Linux installations 71
- Mac installations 65
- Windows installations 8, 42

MATLAB

- Linux, changing path to 78
- Mac, changing path to 60

- running COMSOL Multiphysics on
 - Linux with 90
 - running COMSOL Multiphysics on
 - Mac with 66
 - running COMSOL Multiphysics on
 - Windows with 52
 - Windows, changing path to 52
- Model Library Update
 - configuring on Linux 77
 - configuring on Mac 59
 - configuring on Windows 26
- multicore computing 3
- multiprocessor computing 3
- N** Named Single User License
 - definition 4
 - Linux, and 76, 81
 - network access of license 4
- O** operating system 3
- options file 81
- P** passcode 7
- physical address 8
- port number 17
- previous installation 2
- Pro/ENGINEER
 - LiveLink for 29
- product downloads 1
 - COMSOL Access, and 6
 - Linux, DVD 73
 - Mac 53
 - Mac, DVD 56
 - troubleshooting 91
 - Windows 7
 - Windows, COMSOL installer 10, 72
 - Windows, DVD 11
- product updates 1
 - COMSOL Access, and 6
- proxy server
 - for software updates 25
 - Linux installations 78
 - Mac installations 59
 - Windows installations 21
- R** Remote Desktop 4, 21
- remove feature 15
- root 82
- S** SERIAL line, license file 37
- SERVER line, license file 36
- shared-memory computing 3
- software license agreement 3
- Solid Edge
 - LiveLink for 31
- SolidWorks
 - LiveLink for 28
- SpaceClaim
 - LiveLink for 31
- system requirements 1, 2
- T** technical support, contacting 91
- technical support, website 1
- three-server redundancy 17
- trial license 5
 - Linux 71
 - Mac 53
 - Windows 7
- troubleshooting license errors 91
- tutorials, installation 91
- tutorials, videos 1
- U** unattended installation
 - Linux 77
 - Mac 59
 - Windows 25
- uninstalling COMSOL
 - Linux 77
 - Mac 59
 - Windows 23
- updates, product 1
 - COMSOL Access 6
- USE_SERVER line, license file 36

- user interface, cross-platform 43, 46
- utility program, Linux 80
- utility program, Mac 61
- utility program, Windows 34
- V** vendor daemon
 - Linux installations 80
 - Mac installations 61
 - Windows installations 34
- VENDOR line, license file 36
- videos
 - installation 91
 - tutorials 1
- volume serial number 9
- W** web browsers, for Linux 76
 - Windows Remote Desktop 4, 21
- X** xterm program 90

